



UNC
INSTITUTE FOR
THE ENVIRONMENT

Visualization Environment for Rich Data Interpretation (VERDI 1.4.1): User's Manual

U.S. EPA Contract No. EP-W-09-023, "Operation of the Center for
Community Air Quality Modeling and Analysis (CMAS)"

Prepared for: William Benjey and Donna Schwede
U.S. EPA, ORD/NERL/AMD/APMB
E243-04
USEPA Mailroom
Research Triangle Park, NC 27711

Prepared by: Liz Adams and Darin Del Vecchio
Institute for the Environment
The University of North Carolina at Chapel Hill
137 E. Franklin St., CB 6116
Chapel Hill, NC 27599-6116

Date: April 30, 2013

Contents

1	Introduction.....	1
1.1	Background.....	1
1.2	Where to Obtain VERDI.....	2
1.3	Where to Obtain VERDI Documentation.....	6
1.4	Help Desk Support for VERDI.....	8
1.5	Future VERDI Development.....	8
2	Requirements for Using VERDI.....	9
2.1	Java Runtime Environment.....	9
2.2	Memory and CPU Requirements.....	9
2.3	Requirements to Run VERDI Remotely.....	10
2.4	Graphics Requirements.....	10
2.5	Display Properties.....	10
3	VERDI Installation Instructions.....	10
3.1	VERDI Installation.....	10
3.2	Installation Instructions for Linux and Other Non-Windows JRE™ 6 Supported System Configurations.....	11
3.3	Installation Instructions for computer that that requires a JRE™ 6 other than what was provided in the distribution:.....	11
3.4	Installation Instructions for Windows.....	12
3.5	Setting VERDI Preferences.....	16
4	Starting VERDI and Getting Your Data into VERDI.....	18
4.1	Starting VERDI.....	18
4.1.1	Windows.....	18
4.1.2	Linux and Other Non-Windows JRE™ 6 Supported System Configurations.....	18
4.2	Main Window.....	19
4.3	Floating the Dataset and Formula Panes.....	20
5	Navigating VERDI's Main Menu Options.....	20
5.1	File Menu Options.....	21
5.1.1	Open Project.....	21

5.1.2	Save Project	21
5.1.3	View Script Editor	21
5.2	Plots Menu Options.....	22
5.2.1	Undock All Plots.....	22
5.2.2	Animate Tile Plots	22
5.3	Window Menu Options.....	23
5.3.1	Datasets and Formulas	23
5.3.2	List of Plots	23
5.4	Help Menu Options.....	24
6	Working with Gridded Datasets.....	24
6.1	Gridded Input File Formats.....	24
6.1.1	Model Formats	24
6.1.2	Observational Data Formats	24
6.2	Example Datasets.....	25
6.3	Adding and Removing a Dataset from a Local File System.....	26
6.4	Adding and Removing a Dataset from a Remote File System	28
6.4.1	Remote File Browser	28
6.4.2	Adding Additional Remote Hosts	31
6.5	Variables List.....	32
6.6	Time Steps, Layers Panels	33
6.7	Domain Panel.....	33
6.8	Saving Projects.....	34
7	Working with Formulas	34
7.1	Adding and Removing a Formula.....	34
7.2	Example Formulas	37
7.3	Selecting a Formula for Plotting.....	37
7.4	Saving Formulas	37
7.5	Time Step Range, Layer Range, and Edit Domain	37
8	Working with Area Files	38
8.1	Area File Formats	38
8.2	Example Area File	38
8.3	Adding and Removing an Area File	38
8.4	Areas List.....	39
8.5	Areal Interpolation	39
9	Spatial and Temporal Data Subsetting.....	43

9.1	Specify Time Step Range.....	44
9.2	Specify Layer Range.....	44
9.3	Specify Domain Range	45
9.4	Rules of Precedence for Subsetting Data.....	47
10	Creating Plots	48
10.1	Fast Tile Plot.....	49
10.1.1	Time Selection and Animation Controls.....	49
10.1.2	Layer Selection	50
10.1.3	Grid Cell Time Aggregate Statistics	50
10.2	Areal Interpolation Plot.....	51
10.2.1	Option Pull-down Menu Item	51
10.2.2	Areal Values for Polygon Segment.....	55
10.2.3	View and Export Areal Plot Data in Spreadsheet Format	56
10.2.4	Export Areal Plot Data to Shapefiles	57
10.3	Vertical Cross Section Plot	58
10.4	Time Series Plot.....	60
10.5	Time Series Bar Plot	60
10.6	Scatter Plot.....	61
10.7	Vector Plot	63
10.8	Contour Plot.....	65
11	Plot Menu Bar	65
11.1	File Menu Options	67
11.2	Configure Menu Option.....	67
11.2.1	Configuring Plots	67
11.2.2	Loading and Saving Configuration	70
11.3	Controls Menu Options.....	71
11.3.1	Zoom Using the Left Mouse Button	71
11.3.2	Zoom Using the Right Mouse Button.....	71
11.3.2.1	Vector Plot.....	71
11.3.2.2	Fast Tile Plot and Areal Plot	72
11.3.3	Probing Values at Specific Points.....	73
11.3.4	Probing a Domain Region of Data.....	74
11.3.5	Set Data Ranges	75
11.3.6	Showing Latitude and Longitude.....	77
11.4	Plot Menu Options	78
11.4.1	Time Series Plots	79

- 11.4.2 Animate Plots.....79
- 11.4.3 Add Overlays80
 - 11.4.3.1 Observational Data Overlays 80
 - 11.4.3.2 Vector Overlays..... 82
- 11.5 GIS Layer Options (Fast Tile Plot).....84
 - 11.5.1 Add Map Layers84
 - 11.5.2 Configure GIS Layers (Fast Tile Plot).....87
 - 11.5.3 Set Current Maps as Default Location.....89
- 12 Supported Grid and Coordinate Systems (Map Projections).....89**
 - 12.1 I/O API-formatted Data89
 - 12.2 CAMx Gridded Data.....93
- 13 I/O API Utilities, Data Conversion Programs, and Libraries96**
- 14 Contributing to VERDI Development96**
- 15 Known Bugs.....97**
- 16 Mathematical Functions.....97**
- 17 VERDI Batch Script Editor100**
 - 17.1 Specify hour/time step formula in batch script mode106
 - 17.2 Mathematical function capability in batch script mode.....108
 - 17.2.1 Batch Script Example: Maximum Ozone – layer 1 (Figure 17-11).....108
 - 17.2.2 Batch Script Example : Minimum Ozone – layer 1 (Figure 17-12)109
 - 17.2.3 Batch Script Example : Mean of Ozone – layer 1 (Figure 17-13).....110
 - 17.2.4 Batch Script Example : Sum of Ozone – layer 1 (Figure 17-14).....111
- 18 Command Line Scripting112**
 - 18.1 Example Command Line Script for Linux Users112
 - 18.2 Example Command Line Script for Windows Users.....113
- 19 Areal Interpolation Calculations.....118**
- 20 Licenses for JAVA Libraries used by VERDI119**
- Acknowledgments120**
 - Data Contributions120
 - Data Reader Contributions.....120
 - I/O Service Provider (IOSP) Interface for CAMx:120
 - Incorporating the IOSP into netCDF netcdf-java v4.1 Library:120

Figures

Figure 1-1. Top of Main VERDI Web Site Page.....	3
Figure 1-2. Downloading VERDI from the CMAS Web Site, Step 1.....	4
Figure 1-3. Downloading VERDI from the CMAS Web Site, Step 2.....	5
Figure 1-4. Downloading VERDI from the CMAS Web Site, Step 3.....	6
Figure 1-5. Getting Documentation on VERDI from the CMAS Web Site.....	7
Figure 1-6. VERDI Documentation on the CMAS Web Site.....	8
Figure 3-1. VERDI Setup Wizard.....	13
Figure 3-2. License Agreement.....	13
Figure 3-3. Selecting an Installation Directory.....	14
Figure 3-4. Setting the Start Menu Folder.....	14
Figure 3-5. File Extraction.....	15
Figure 3-6. Installation Complete.....	16
Figure 4-1. Starting VERDI in Windows.....	18
Figure 4-2. VERDI Main Window.....	20
Figure 5-1. VERDI Main Menu Options.....	21
Figure 5-2. Animate Plots Dialog and Fast Tile Plots.....	23
Figure 6-1. Observational File ASCII Format.....	25
Figure 6-2. Open Dataset File Browser.....	26
Figure 6-3. Datasets Pane Displaying Information about a Dataset.....	27
Figure 6-4. Available Hosts in the Remote File Access Browser.....	28
Figure 6-5. Select one or more variables from Remote Dataset.....	29
Figure 6-6. Remote Dataset Labeled with Number at End of the Filename.....	31
Figure 6-7. Edit configure.properties file to add a remote host.....	32
Figure 6-8. Right Click on Variable in Dataset Pane.....	33
Figure 6-9. Dataset Metadata Information.....	34
Figure 7-1. Adding Multiple Variables to Formula Editor.....	36
Figure 8-1. Areas Pane.....	39
Figure 8-2. Open Area File Browser.....	40
Figure 8-3. Open Area File: Select Name Field.....	40
Figure 8-4. Coordinate System.....	41
Figure 8-5. Projection Information.....	41

Figure 8-6. Additional Data Fields appear depending on projection selected.....41

Figure 8-7. Area Name Fields available for Shapefile43

Figure 9-1. Specify Time Step Range.....44

Figure 9-2. Edit Layer Range in Formula Pane45

Figure 9-3. Using the Slider to View the Domain Panel46

Figure 9-4. Edit Domain Dialog Box.....46

Figure 9-5. Error obtained when incompatible subset domains are created using the Dataset pane48

Figure 10-1. Fast Tile Plot49

Figure 10-2. Areal Plot: Area Average52

Figure 10-3. Areal Plot: Area Totals.....53

Figure 10-4. Areal Interpolation Plot: Show Grid (Gridded Data).....54

Figure 10-5. Areal Interpolation Plot: Show Selected Areas.....55

Figure 10-6. Areal Values for Polygon Segments56

Figure 10-7. Right Click on Area Plot.....57

Figure 10-8. Area Information Spreadsheet.....57

Figure 10-9. Export Spreadsheet.....57

Figure 10-10. Name and save spreadsheet.....57

Figure 10-11. Export Shapefile.....58

Figure 10-12. Name and save shapefile.....58

Figure 10-13. Vertical Cross Section Plot59

Figure 10-14. Vertical Cross Section Dialog Box59

Figure 10-15. Time Series Plot60

Figure 10-16. Time Series Bar Plot61

Figure 10-17. Scatter Plot62

Figure 10-18. Scatter Plot Dialog Box.....62

Figure 10-19. Scatter Plot Export Data into a CSV file.....63

Figure 10-20. Vector Plot64

Figure 10-21. Vector Plot Dialog Box64

Figure 10-22. Contour Plot65

Figure 10-23. Contour Plot Menu Options65

Figure 11-1. Fast Tile and Areal Plot Pull-down Menu Options.....66

Figure 11-2. Vector Plot Pull-down Menu Options.....66

Figure 11-3. Configure Plot, Titles Tab.....69

Figure 11-4. Configure Plot, Color Map Tab69

Figure 11-5. Configure Plot, Labels Tab69

Figure 11-6. Configure Plot, Other Tab.....69

Figure 11-7. Example Plot with Tick Marks reduced for the Legend and Range Axis.....70

Figure 11-8. Right Click on Tile Plot to Zoom Out.....72

Figure 11-9. Right Click on Fast Tile Plot to access Zoom Out Option.....73

Figure 11-10. Click on Plot to Probe: Data Value Shown in Lower Left of VERDI, Grid
Values Shown in Lower Right74

Figure 11-11. Spreadsheet Showing Probed Values for Region of Interest75

Figure 11-12. Select Set Row and Column Ranges.....76

Figure 11-13. Enter Row and Column Values.....77

Figure 11-14. Lat/Lon Values Shown in Lower Right of VERDI.....78

Figure 11-15. Plot Menu Options79

Figure 11-16. Animate Plot Dialog Box80

Figure 11-17. Fast Tile Plot Observation Dialog.....81

Figure 11-18. Fast Tile Plot with Multiple Observational Data Overlays with Grid Lines.....82

Figure 11-19. Vector Overlay Dialog Box83

Figure 11-20. Wind Vector Overlay on an Ozone Fast Tile Plot84

Figure 11-21. Plot Menu Options84

Figure 11-22. Add Map Layers.....85

Figure 11-23. shape2bin command usage.....86

Figure 11-24. Manage Layers Dialog Box87

Figure 11-25. Add Layer Pop-up Window88

Figure 11-26. Edit Layer Pop-up Window89

Figure 12-1. Lambert Conformal Conic Map Projection Example Plot.....90

Figure 12-2. Polar Stereographic Map Projection Example Plot.....91

Figure 12-3. Mercator Map Projection Example Plot.....92

Figure 12-4. UTM Map Projection Example Plot93

Figure 12-5. Example CAMx diagnostic text file.....94

Figure 12-6. Models-3 I/O API Map Projection Parameters for Lambert94

Figure 12-7. Sample Projection File: camxproj.txt.....95

Figure 12-8. CAMx Example Plot.....95

Figure 17-1. File: View Script Editor100

Figure 17-2. Open Pop-up Window.....101

Figure 17-3. Top of Sample Script File – VERDI_1.4.1/data/scripts/file_patterns.txt102

Figure 17-4. Bottom of Sample Script File – VERDI_1.4.1/data/scripts/tile_patterns.txt102

Figure 17-5. Close Dataset(s) Warning Message103

Figure 17-6. Highlight Text to Select Task and Click Run104

Figure 17-7 Successful Batch Script Run Message	105
Figure 17-8. Unsuccessful Batch Script Run Message: File not found	105
Figure 17-9. Plot Image Generated by Task Block.....	106
Figure 17-10. Fast Tile Plot of Ozone at Time step 17, Layer 1	108
Figure 17-11. Fast Tile Plot of Maximum Air Temperature (aggregated over 25 time steps)	109
Figure 17-12. Fast Tile Plot of Minimum Ozone (aggregated over 25 time steps)	110
Figure 17-13. Fast Tile Plot of Mean Ozone (aggregated over 25 time steps).....	111
Figure 17-14. Fast Tile Plot of the Sum of Ozone (aggregated over 25 time steps)	112
Figure 18-1. Location of run.bat script in Windows.....	114
Figure 18-2. Submit run.bat script from Run command.....	115

1 Introduction

1.1 Background

This manual describes how to use the Visualization Environment for Rich Data Interpretation (VERDI). VERDI is a flexible and modular Java-based visualization software tool that allows users to visualize multivariate gridded environmental datasets created by environmental modeling systems such as the Community Multiscale Air Quality (CMAQ) modeling system and the Weather Research and Forecasting (WRF) modeling system. These systems produce files of gridded concentration and deposition fields that users need to visualize and compare with observational data both spatially and temporally. VERDI can facilitate these types of analyses.

Initial development of VERDI was done by the Argonne National Laboratory for the U.S. Environmental Protection Agency (EPA) and its user community. Argonne National Laboratory's work was supported by the EPA through U.S. Department of Energy contract DE-AC02-06CH11357. Further development has been performed by the University of North Carolina Institute for the Environment under U.S. EPA Contract No. EP-W-05-045 and EP-W-09-023, by Lockheed Corporation under U.S. EPA contract No. 68-W-04-005, and Argonne National Laboratory. VERDI is licensed under the Gnu Public License (GPL) version 3, and the source code is available through verdi.sourceforge.net. Instructions for developers within the community are included in the Developer User Guide (see Section 1.3). VERDI is supported by the Community Modeling and Analysis System (CMAS) Center under U.S. EPA Contract No. EP-W-09-023. The batch script and VERDI Script Editor were developed and documented under U.S. EPA Contract No. EP-D-07-102, through an Office of Air Quality Planning and Standards project managed by Kirk Baker. The CMAS Center is located within the Institute for the Environment at the University of North Carolina at Chapel Hill.

This guide describes VERDI version 1.4.1 released in April 2013.

The following are useful web links for obtaining VERDI downloads and support:

1. VERDI Visualization Tool web site:
<http://www.verdi-tool.org>
2. CMAS download page for users of VERDI:
<http://www.cmascenter.org/download/software.cfm>
3. CMAS SourceForge.net website for developers of VERDI:
<http://sourceforge.net/projects/verdi/>
4. VERDI Frequently Asked Questions (FAQs):
<http://www.verdi-tool.org/VERDI.faq.html>

5. To query M3USER listserv for VERDI related technical support questions and answers:
<http://lists.unc.edu/read/?forum=m3user>
6. To query bugs and submit bug reports, questions, and/or requests:
http://bugz.unc.edu/enter_bug.cgi?product=VERDI
(If you do not already have a login and password, click the “Home” link for instructions on how to obtain them.)

1.2 Where to Obtain VERDI

You can download the latest version of VERDI from <http://www.verdi-tool.org/> (see Figure 1-1). When you click on the link to download VERDI, you will be sent to the CMAS Model Download Center. To download and install VERDI, follow the instructions below, skipping step 2. Alternatively, you may also begin at the CMAS web site <http://www.cmascenter.org>, and follow the instructions below:

1. Log in using an existing CMAS account, or create a new CMAS account.
2. Hover the cursor over the Download Center link on the left-hand side of the web site and choose MODELS from the menu that appears.
3. Select a model family to download, as shown in Figure 1-2. Use the pull-down list to select VERDI, and then click Submit.
4. Select the product you wish to download, as shown in Figure 1-3. Also specify the type of computer you are planning to run VERDI on (such as Linux PC, Windows, or Other) from the items in the scroll list. Note that the compilers question is not relevant for VERDI so it can be skipped. Finally, click Submit.
5. In the table that appears, follow the links to the Linux or Windows installation instructions, the release notes file, the user's manual, the test documentation, and either a zip archive for Windows or a gzipped tar archive for Linux (see Figure 1-4).

Figure 1-1. Top of Main VERDI Web Site Page




Figure 1-2. Downloading VERDI from the CMAS Web Site, Step 1




Figure 1-3. Downloading VERDI from the CMAS Web Site, Step 2




Figure 1-4. Downloading VERDI from the CMAS Web Site, Step 3

The screenshot shows the CMAS website interface. The main content area is titled "VERDI 1.4" and contains the following text:

Installation instructions, documentation, and software for VERDI 1.4.

NOTE: Save the files that you download into a common directory.

File type	Download link and file name (Right click on link and choose "Save Target As")	Release date
Linux installation instructions	View	05/31/2011
Mac installation instructions	View	05/31/2011
Windows installation instructions	View	05/31/2011
VERDI version 1.4 RELEASE-NOTES	View	05/31/2011
User's Guide (PDF)	Download	05/31/2011
User's Guide (HTML)	View	05/31/2011
Test Documentation	Download	05/31/2011
Windows Installation File	Download	05/31/2011
Gzipped tar archive for Linux	Download	05/31/2011
Zip archive of shape2bin	Download	05/31/2011
DMG File for Mac OSX	Download	05/31/2011
Example Data Files	Example Data is provided in the release archive	05/31/2011
Developer Instructions	View	05/31/2011

The left sidebar contains a navigation menu with links such as HELP DESK, DOWNLOAD CENTER, and CONFERENCE & MEETINGS. Below the menu is a "User Details" section showing the user is logged in as lizadams@email.unc.edu. At the bottom of the page, there is a footer for the Community Modeling and Analysis System (CMAS) with contact information.

1.3 Where to Obtain VERDI Documentation

Documentation is available in several locations, described below. Each location provides links to the available documentation for VERDI, which can be viewed in your web browser or downloaded and saved to your computer.

- The VERDI download page on the CMAS website (accessed using step 4 in Section 1.2) contains links to all of the available documentation.
- On the left-hand side of the www.cmascenter.org web site, you can hover the cursor over the Help Desk link and choose DOCUMENTATION from the menu that appears. Select the product documentation that you want from the drop-down list (Figure 1-5) and click Submit. Select the model release from the drop-down list and click Search. The resulting documentation pane shows that the available documentation for the chosen release of VERDI.
- From the www.verdi-tool.org web site, there are two ways to access the VERDI documentation on the www.cmascenter.org model documentation web page: (1) A link near the top of the www.verdi-tool.org home page sends you to a new page where you choose the model version. When you click submit, you are taken to the www.cmascenter.org VERDI documentation web page. (2) Direct links from a box on the right-hand side of the www.verdi-tool.org home page take you to the documentation

available for VERDI. Figure 1-6 shows the list of documentation that is available for download.

Figure 1-5. Getting Documentation on VERDI from the CMAS Web Site





Figure 1-6. VERDI Documentation on the CMAS Web Site



1.4 Help Desk Support for VERDI

You are encouraged to check the [VERDI FAQs](#), search archived support requests using the web-based Bugzilla system, search the [M3USER listserv](#) for VERDI-related technical support questions, and report errors and/or requests for enhancement to the m3user forum. The m3user forum is supported by the community and also by CMAS to help users resolve issues and identify and fix bugs found in supported software products.

1.5 Future VERDI Development

As stated in Schwede et al. (2007),¹ “VERDI is intended to be a community based visualization tool with strong user involvement.” The VERDI source code is available to the public under a GPL license at <http://sourceforge.net/projects/verdi/>. This allows users who wish to make improvements to VERDI to download the software, and to develop enhancements and improvements that they feel may be useful to the modeling community. Examples could include user-developed readers for additional file formats and modules for additional plot types. Users may wish to contribute data analysis routines, such as adding the ability to do bilinear

¹ Schwede, D., N. Collier, J. Dolph, M.A. Bitz Widing, T. Howe, 2007: A New Tool for Analyzing CMAQ Modeling Results: Visualization Environment for Rich Data Interpretation (VERDI). Proceedings, CMAS 2007 Conference.

interpolation (smoothing), or to contribute other enhancements to the existing plot types. The direction of future development will depend on the resources and the needs of the modeling community. If you are interested in contributing code to VERDI, please review the information in Chapter 14, "Contributing to VERDI Development."

2 Requirements for Using VERDI

2.1 Java Runtime Environment

VERDI requires version 6 of the Java Standard Edition Runtime Environment (JRE). The JRE™ 6 is provided as part of the VERDI release for Linux 32 bit and Windows. Instructions for how to download JRE™ 6 and the additional third-party libraries for Linux 64 bit are provided in section 3.2. On Windows 32 bit machines, the contour plot requires DirectX SDK. Download and install this software if you obtain the following error when running the contour plot.



<http://www.microsoft.com/en-us/download/details.aspx?id=6812>

2.2 Memory and CPU Requirements

VERDI's memory and CPU requirements largely depend on the size of the datasets to be visualized. Small datasets can be visualized and manipulated using less than 1024 megabytes of RAM, while larger datasets may need considerably more. If you are using datasets that require either more or less than 1024 MB of memory, you can change the default maximum memory setting used by VERDI:

- On Windows, edit the Verdi.ini file to specify a different heap size from the default 1024M.
- On Linux or another Unix platform, you can edit verdi.sh and replace the 1024 in `-Xmx1024M` with a different value; for example, `-Xmx2048M` will allow VERDI to access up to 2048MB (or 2GB) of RAM.

Note that even slower CPUs can quickly view and animate smaller datasets, whereas larger datasets can take longer. Initially, VERDI's performance was slow when it was used across the

network via ssh. This problem was addressed in version 1.1 with the addition of the Fast Tile Plot. Beginning with version VERDI 1.4, memory was more effectively managed. As a user opens new Fast Tile plots or other plot types, the memory requirements increase. As the user then closes the plots, the memory is correctly released by VERDI.

2.3 Requirements to Run VERDI Remotely

VERDI may be used to run on a remote compute server and have the graphics display locally on your desktop machine (Unix workstation, Mac, or PC) using the Fast Tile Plot. Your computer needs to be configured to run X-Windows. Typically, you will connect to the remote compute server using secure shell (SSH). If you are using an X-Server and wish to generate 3-D plots using Open GL, you need to turn on Open GL support within the X-Server.

2.4 Graphics Requirements

Three-dimensional contour plots require a graphics card with OpenGL or DirectX capability. By default VERDI uses OpenGL for 3D rendering. If you would like to use DirectX instead, add the line: `j3d=-Dj3d.rend=d3d` to the `verdi.ini` file.

2.5 Display Properties

VERDI works best on screen displays that have been set to a high or perhaps the highest screen resolution (1280 × 1024 pixels for Windows XP machines or 1440 × 900 for Mac or Windows Vista). To adjust your screen resolution for a Windows XP machine, right click on your desktop and then click on the Settings tab in the pop-up window. Use the slider under the screen resolution section to set the resolution to 1280 × 1024 pixels. You may need to reboot your computer for this modified screen setting to take effect. For Windows Vista, right click on your desktop and click on Graphics Properties. In the pop-up window, click on Display Settings. To adjust the screen resolution on a Mac, go to Applications and double click on System Preferences, then under Hardware select Displays. Select 1440 × 900.

3 VERDI Installation Instructions

3.1 VERDI Installation

Installing VERDI on a Windows operating system is accomplished by running a standard installer program. For Linux and other non-Windows platforms, VERDI is distributed as a gzipped tar file that contains the executable application and the third-party libraries needed for VERDI. Currently, the VERDI distributions provide a platform-specific Java Runtime Environment 6.0 (see Section 3.3) for Windows and Linux. Note that the version of Java provided with VERDI includes the JAVA 3D and JAI packages to support the three-dimensional plots used by VERDI's contour plot. For more information on supporting the contour plot on your non-windows platform of interest, see the Java3D discussion section 3.2 that follows.

Instructions on how to download JRE™ 6 for other system configurations that run it are also provided.

3.2 Installation Instructions for Linux and Other Non-Windows JRE™ 6 Supported System Configurations

Follow these instructions to install VERDI:

1. tar -xvf verdi_1.4.1.tar into a location where you would like to install VERDI.
2. Edit verdi_1.4.1/verdi.sh: Change the path for the VERDI_HOME variable to reflect the location where VERDI was installed (e.g., VERDI_HOME=/usr/local/verdi)
3. VERDI should now run if you execute the verdi.sh executable script (e.g., ./verdi.sh).

3.3 Installation Instructions for computer that that requires a JRE™ 6 other than what was provided in the distribution:

1. Download Java 6 for your platform from <http://www.java.com/en/download/manual.jsp>.
2. Download Java3D
 - a. For all platforms, go to <http://java.sun.com/javase/technologies/desktop/java3d/>
 - b. Go to download section, click on Download Java 3D 1.5.1 Software, select your platform, agree to license agreement, and continue.
 - c. mv java3d-1_5_1-linux-i586.bin to the jre1.6.0_06 directory
 - d. chmod a+x java3d-1_5_1-linux-i586.bin
 - e. ./java3d-1_5_1-linux-i586.bin (this will place the lib/ext and lib/i386 files where they are needed)
3. Download JAI 1.1.3
 - a. For all platforms, go to http://download.java.net/media/jai/builds/release/1_1_3/ Select JRE Install (Note JRE is the Java Runtime Environment and needed for running VERDI, JDK is the Java Development Kit, and the JDK is only needed by those who are developing code for VERDI)
 - b. Download the .tar.gz package and untar. This will create a directory "jai-1_1_3".
 - c. Copy the following files:
 - i. cp jai-1_1_3/lib/libmllib_jai.so /path-to-/verdi_1.4.1/jre1.6.0_13/lib/i386

ii. `cp jai-1_1_3/lib/*.jar /path-to-/verdi_1.4.1/jre1.6.0_13/lib/ext`

4. Download JAI ImageIO

- a. Download `jai_imageio-1_1-lib-{yourplatform}.exe` by clicking on it and saying save as. Run the executable by double clicking on it to start the InstallShield Wizard. Specify the Destination Folder as the location where the JRE was installed.

If JRE™ 6 is already installed on your Linux platform, and you would like to use the already installed version, you will need to add Java 3D support. Copy the following files from the version of Java provided in the VERDI release into the `JRE_HOME/bin` directory used by your version of Java:

`j3dcore-d3d.dll`
`j3dcore-ogl.dll`
`j3dcore-ogl-cg.dll`
`j3dcore-ogl-chk.dll`
`j3dutils.dll`

3.4 Installation Instructions for Windows

To install VERDI for Windows, run the installation program `VERDI_1.4.1_Installer.exe` on your Windows machine. Follow the instructions on the installation windows that appear, as shown in Figures 3-1 through 3-6. If you are unable to install VERDI on your computer, please check to see whether your user account is authorized to install software. You may need to request that a user with a computer administrator account install VERDI, or provide you with an account that has permission to install software. For more information about user account types, click Start and select Control Panel and then click on the User Account icon.

Figure 3-1. VERDI Setup Wizard



Figure 3-2. License Agreement




Figure 3-3. Selecting an Installation Directory




Figure 3-4. Setting the Start Menu Folder




Figure 3-5. File Extraction





Figure 3-6. Installation Complete



3.5 Setting VERDI Preferences

The VERDI installation package contains a file called `config.properties.TEMPLATE`. On Windows, this file is copied into the VERDI subdirectory of your USERPROFILE directory (e.g., “C:\Documents and Settings\yourusername\verdi”) and renamed to `config.properties`. On Linux, this file is copied into the `~username/verdi/` subdirectory and renamed to `config.properties`. Users are encouraged to edit this file to specify default directories for saving files, for placing the location of configuration files, and for saving project files. Contents of `config.properties.TEMPLATE`:

```
# This file should be put in $USER_HOME/verdi/ subdirectory
# Please use double backslash for windows platform or slash for UNIX like platforms as file
# Please uncomment the following lines and modify them to suit your local settings

# Windows example settings format
```

```
# verdi.project.home=C:\\Program Files\\VERDI_1.4.1\\project
# verdi.config.home=C:\\Program Files\\VERDI_1.4.1\\config

# Linux example settings format
verdi.project.home=../../data/project
verdi.config.home=../../data/configs
verdi.user.home=../../data/model
verdi.dataset.home=../../data/model
verdi.script.home=../../data/scripts

# WDT default area file folder
verdi.hucData=../../data/hucRegion/

# For VERDI to access remote big netCDF data files

verdi.remote.hosts=terrae.nesc.epa.gov,vortex.rtpnc.epa.gov,garnet01.rtpnc.epa.gov,tulip.rtpnc.e
pa.gov

remote.file.util=/usr/local/bin/RemoteFileUtility

verdi.remote.ssh=/usr/bin/ssh

#on local machine where VERDI is running. Used to hold temporary data file downloaded from
a remote machine

verdi temporary.dir=C:\\temp
```

The items in the config.properties.TEMPLATE file that is installed with VERDI are commented out, and will need to be uncommented by removing the starting ‘#’ sign if you do not want to specify the directories each time a file is loaded or saved. Example settings that are provided in the default file show how to specify the paths to these locations, depending on whether the installation is for a Windows or Linux platform. The verdi.project.home setting specifies the default location from which to load and save projects. The verdi.config.home setting specifies

the default location from which to load and save plot configurations. The `verdi.dataset.home` setting specifies the default location from which to load datasets. The `verdi.script.home` setting specifies the default location from which to load and save batch scripts. Note that VERDI stores the most recently used directory for each of these functions and will go to that directory when you repeat the load or save. The `verdi.hucData` setting specifies the default locations where area shapefiles are located. VERDI will navigate to this directory when the user selects to add a dataset in the Area pane. The `verdi.remote.hosts` setting contains a list of machines that the user can select to browse from when adding a remote dataset using VERDI's Remote File Access capability. The `verdi.remote.util` setting specifies the location of the RemoteFileUtility script for Linux and Mac installations of VERDI. Starting in VERDI version 1.4, the `ui.properties` file was removed, and the user configurable settings such as the default directory location that were previously specified in the `ui.properties` file were moved to the `config.properties` file.


4 Starting VERDI and Getting Your Data into VERDI

4.1 Starting VERDI

4.1.1 Windows

To start VERDI, open the **Start** menu, then highlight the **Programs** directory, followed by the **VERDI** directory, and then select the **VERDI icon**, as shown in Figure 4-1.

Figure 4-1. Starting VERDI in Windows



4.1.2 Linux and Other Non-Windows JRE™ 6 Supported System Configurations

To start VERDI from Linux and other non-Windows JRE™ 6 Supported System Configurations, find the directory where VERDI was installed, then run the `verdi.sh` script. On a Mac go to the `/Applications/verdi_1.4.1` directory and run the `verdi.command` script.


4.2 Main Window

After starting VERDI, the main window will come up on the screen (Figure 4-2). At the top of the main window, there is a menu bar with the main window options (**File, Plots, Window, and Help**). Below the menu bar there are three icons that are shortcuts to some of the options available in the Main Window Menu Bar; the first is an **Open Project** icon, the second is a **Save Project** icon, the third is an icon that allows you to **Undock All Plots**. These shortcuts and the options available in the Main Window Menu Bar are discussed further in Section 5, "Navigating VERDI's Main Menu Options." Next to these three shortcut icons are buttons that list all of the available plot types. To the right of all the plot buttons the Selected Formula is listed. The Selected Formula refers to the formula that has been selected in the **Formula** pane (discussed briefly below and in detail in Section 7), and that will be used to create plots. Below the icons and plot buttons, the window is divided into two main areas: a parameters area on the left side and a plots area on the right side. The parameters area contains three tabbed panes:

- The **Datasets** pane is used to load in the dataset files that you want to work with in this session (this is discussed in Section 6). Once the datasets are loaded, VERDI automatically displays the lists of variables that are in the datasets. To see the variables in a dataset, click on the dataset, and the variables will be displayed in the **Variables** panel underneath the list of datasets. In Version 1.05 and later, if you double click on the name of a variable listed on the variables panel, the variable will automatically be added as a formula on the **Formula** pane and will be the default formula for new plots that are created.
- The **Formula** pane is used to create a formula that refers to the variable and the dataset that you are interested in plotting (see Section 7 for more information). All plots in VERDI are generated from formulas. A formula can be as simple as a single variable from one dataset or it can be an equation that uses variable(s) from one or more datasets.
- The **Areas** pane is used to load area files that are used to create areal interpolation plots (see Section 8 for more information). Area files are defined as shapefiles that contain area features such as watersheds and counties, or any other shapefile that consists of a set of closed polygons.

Any plots that are created are shown in the plots area on the right-hand side of the main window. These plots can be placed into their own movable windows using **Plots>Undock all Plots** on VERDI's main menu, as discussed in Section 5.2.1. The fast tile plot option was added in VERDI version 1.1. As of VERDI 1.4, the tile plot option was removed, since the functionality has been replaced by the fast tile plot; however, there are derivative plots, such as the vector plot, that still use the tile plot code. In a future release, these derivative plots will be migrated to use the Fast Tile Plot as their base. The Fast Tile Plot has an option (**Plot>Add Overlay> Vectors**) to create a Fast Tile Plot of a variable with a vector overlay of wind vectors or other vector types. The Fast Tile Plot with vector overlay should be used as the preferred alternative to the Vector Plot until the Vector Plot is updated in a future release. The functions that are currently enabled for fast tile plots are described in Section 10, "Creating Plots."

Figure 4-2. VERDI Main Window



4.3 Floating the Dataset and Formula Panes

The **Formula**, **Dataset**, and **Areas** panes can each be configured to float, to allow you to position them alongside one another. To allow a pane to float, click the icon at the top of the pane that looks like a rectangle with an angle bracket above the upper right corner. You can then click on the pane and move it independently of the VERDI main window. This is useful when you are entering a formula in the **Formula** pane, if you have difficulty remembering the variables that are in a loaded dataset. Once a pane is unconnected from the frame, the icon changes to be a box with an arrow pointing inward, with the hover over text tip: “Connects this panel to the frame”. Click on the box with the inward arrow to reconnect the panel with the frame. This will return the floating pane back to where it usually lives within the main window.

5 Navigating VERDI's Main Menu Options

Figure 5-1 shows a graphic of the main menu options that are available on the top menu bar in VERDI's main window (Figure 4-2 above). These options are discussed in detail below.

Figure 5-1. VERDI Main Menu Options

VERDI	File	Plots	Window	Help
About VERDI	Open Project Save Project Save Project As	Undock All Plots Animate Tile Plots	Areas Datasets Formulas	VERDI Help Docs About
Preferences	View Script Editor			
Services	Exit			
Quit VERDI				

5.1 File Menu Options

5.1.1 Open Project

Open Project retrieves projects that were saved during a previous session (using the two **Save Project** options described next). Note that when you use a saved project, *it is very important* to load that project into VERDI *before* you load any additional datasets or create any additional variables/formulas. If you load a dataset that is not part of the previously saved project and then try to open a previously saved project, you will get a message that says “All currently loaded datasets will be unloaded”, and will be asked if you want to continue.

5.1.2 Save Project

The **Save Project** and **Save Project As** options save dataset lists and associated formulas as a “project” for later re-use.

Note that plots are not saved with a project; only datasets and formulas are saved. If you wish to save a plot configuration for later use, see Section 11.2.2, “Loading and Saving configuration.”

5.1.3 View Script Editor

The **View Script Editor** allows users to modify and run batch scripts within VERDI. Three sample script files are provided with the VERDI distribution under the \$VERDI_HOME/data/scripts directory. On a Windows machine the \$VERDI_HOME is typically C://Program Files//VERDI_1.4.1. Use the Open pop-up window to specify eps.txt, one of the sample script files. The contents of the eps.txt will be displayed in the Script Editor in the right side of the VERDI window. Modify it to specify the local directory path name for the sample data files, the formulas, the type of plots, and the image format. The plots are not rendered within VERDI, but may be viewed using an image viewer. The batch scripting language is described in the sample script files, and will be described in more detail in Section 17: VERDI Script Editor.

5.2 Plots Menu Options

VERDI opens a single window for plots, to the right of the **Dataset**, **Formula**, and **Area** panes. As plots are created (each in its own sub-window), the most recent plot is displayed on top of previously created plots. Each plot has a tab beneath it listing the type of plot and the formula used to create it. If you want to view a previously created plot, select the tab associated with its sub-window underneath the current plot, and the desired plot will be brought to the front.

5.2.1 Undock All Plots

As with the **Dataset**, **Formula**, and **Area** panes (Section 4.3), plot sub-windows can be undocked or externalized so that you can move them into separate, floating windows. This allows side by side comparisons of plots. Note that undocking is performed only on previously created plots; any newly created plots are created within the VERDI main window.

5.2.2 Animate Tile Plots

This option opens an **Animate Plots** dialog box (Figure 5-2) that allows you to select one or more plots, select a subset of the time range, and create an animated GIF file. There is also a separate way to create a Quicktime movie instead of a GIF, if desired.

Within the **Animate Plots** dialog box, you can **select plot(s)** to animate by clicking the check box beside each plot name.


You can choose to animate a single plot, or animate multiple plots synchronously. To view multiple animated plots synchronously, undock the plots (see Section 5.2.1) and move them so that they are located side by side for visual comparison during the animation.

Once a plot has been selected, you can **select the time range** by specifying both the **starting time step** and **ending time step** of the animation.

To create an animated GIF, check the **Make Animated GIF(s)** option in the **Animate Plots** dialog box. In the **Save** dialog box that appears, select the directory in which to store the file and the name to use for the animated GIF, then click the save button. When saving as an animated GIF, when multiple plots are selected, each animated plot will be saved to a separate animated GIF file. For example, if three plots were selected, the animated plots would be saved as <filename>-1.gif, <filename>-2.gif, <filename>-3.gif. You can view the animated GIF by opening the file in a web browser.

Creating a Quicktime movie is also an option, but this is not done through the **Plots>Animate Tile Plots** main menu option. Instead, use the **Plot** menu option found at the top of each individual plot to make a Quicktime movie.

Figure 5-2. Animate Plots Dialog and Fast Tile Plots



5.3 Window Menu Options

The **Window** menu provides an alternate way to select windows/panes to be brought to the front, and provides the same function as clicking on the tabs at the bottom of the windows/panes.

5.3.1 Datasets and Formulas

Select from the **Window** pull-down menu to bring to the front either the **Areas** pane, **Datasets** pane or **Formulas** pane when those panes are docked.

5.3.2 List of Plots

The **Window** pull-down menu is automatically updated each time a plot is created in a VERDI session; each entry in the plot list indicates the type of plot and the formula used. Clicking on a given plot entry brings that plot to the front for viewing. Alternatively, you can bring a plot to the front by selecting the desired **plot tab** underneath the plots area of the main window. As in the menu entries, each **plot tab** is labeled with the plot type and the formula used.

5.4 Help Menu Options

The **Help** pull-down menu contains two items that you can use to learn more about VERDI. When you select **VERDI Help Docs**, the VERDI user's manual is displayed in a VERDI Help window. This window is not searchable, but it does allow you to navigate via hyperlinks in the Table of Contents, and to scroll down and read the user's manual. When you select **About** a pop-up window that contains the name of the product, the version number, and the date the software was built is displayed.

6 Working with Gridded Datasets

6.1 Gridded Input File Formats

6.1.1 Model Formats

VERDI currently supports visualizing files in the following formats: CMAQ Input/Output Applications Programming Interface (I/O API) netCDF, WRF netCDF, and CAMx (UAM-IV), and ASCII format (for observational data). VERDI uses version 4.1 of the netCDF java I/O library (<http://www.unidata.ucar.edu/software/netcdf-java>).

The CMAQ I/O API was designed as a high-level interface on top of the netCDF Java library. (see <http://www.baronams.com/products/ioapi> and <http://www.unidata.ucar.edu/software/netcdf/> for further info). The I/O API library provides a comprehensive programming interface to files for the air quality model developer and model-related tool developer, in both FORTRAN and C/C++. I/O API files are self-describing and include projection information within the gridded dataset. See section 12 for additional information on what projections and gridded data formats are supported by VERDI.

netCDF and I/O API files are portable across computing platforms. This means that these files can be read regardless of what computer type or operating system you are using. There are routines available to convert data to these formats or new code can be written and contributed to VERDI for use by the community. Discussion of the I/O API conversion programs and how to use them can be found in Section 13, "I/O API Utilities, Data Conversion Programs, and Libraries." If you write a routine for VERDI to read gridded data from other formats, please consider contributing your code to the user community using sourceforge.net, as described in Section 14.

6.1.2 Observational Data Formats

Observational data in ASCII format can be obtained from EPA's Remote Sensing Information Gateway - RSIG (<http://badger.epa.gov/rsig>). To use a consistent set of units, between the model data and the observational data, the user may need to import the ASCII data into an Excel spreadsheet to do a unit conversion. VERDI doesn't allow the user to use an observational variable to create a formula, so conversions to different units should be done within an Excel spreadsheet. Import the file ASCII file that is generated by RSIG into Excel, change the units to

match the units found in the gridded model data file and then save using a tab delimited ASCII file format.

The observational data ASCII format recognized by VERDI is an ASCII file with tab-separated columns where the first four columns are provided in the order shown in Figure 6-1 and one or more additional columns are arbitrary but must have the header format 'name(units)' as shown in Figure 6-1. Spreadsheet programs can be used to edit and write the files by choosing ASCII output and tab as the delimiting character (instead of comma). Data within a column must be complete, as empty fields within a column will cause VERDI to be unable to read the observational data. VERDI 1.4.1 allows the user to specify an alphanumeric value (either numbers and/or letters) for the fourth column (Station ID).

Figure 6-1. Observational File ASCII Format

Timestamp (UTC)	LONGITUDE (deg)	LATITUDE (deg)	STATION (-)	pm25 (ug/m3)
2005-08-26T00:00:00-0000	-121.7842	37.6875	060010007	11.0000
2005-08-26T00:00:00-0000	-122.3991	37.7660	060750005	12.0000
2005-08-26T00:00:00-0000	-122.2034	37.4829	060811001	21.0000
2005-08-26T00:00:00-0000	-121.8950	37.3485	060850005	16.0000
2005-08-26T01:00:00-0000	-121.7842	37.6875	060010007	21.0000
2005-08-26T01:00:00-0000	-122.3991	37.7660	060750005	22.0000
2005-08-26T01:00:00-0000	-122.2034	37.4829	060811001	19.0000
2005-08-26T01:00:00-0000	-121.8950	37.3485	060850005	20.0000
2005-08-26T02:00:00-0000	-121.7842	37.6875	060010007	28.0000

Alternatively, users may use a converter such as AIRS2M3 (see Chapter 13) to convert ASCII observational data into I/O API "observational-data" files.

6.2 Example Datasets

Several example datasets are provided under the \$VERDI_HOME/data directory. For example:

Windows: C:\Program Files\VERDI 1.4.1\data

Mac: /Applications/verdi_1.4.1/data/

Linux: \$VERDI_HOME/verdi_1.4.1/data

These datasets may be used to re-create example plots that are provided in this user guide, including a tile plot with observational data overlay in Section 11.4.3, and the example datasets for the various dataset projections that VERDI supports including LCC, polar stereographic, UTM and Mercator. The data directory currently contains four subdirectories:

1. CAMx – contains sample CAMx dataset and camxproj.txt file
2. hucRegion – contains Hydrologic Unit (HUC) shapefiles for region 3 (southeast US)
3. Model – contains sample WRF and CMAQ I/O API datasets
4. Obs – contains an ASCII formatted observational dataset (Chapter 6-1), and an observational dataset created by airs2m3 converter (Chapter 13).

6.3 Adding and Removing a Dataset from a Local File System

To load a data set from a local file system, press the yellow **plus** button at the top of the **Datasets** pane. A file browser (Figure 6-2) allows you to select a dataset for use in VERDI. Support for loading data from a remote file system has been added beginning in version 1.4. The use of the yellow **plus remote** button will be discussed in Section 6.4.

After you select a dataset, VERDI will load header information and display the available variables, time steps, layers, and domain used by the file in the **Datasets** pane (Figure 6-3). (The actual model data are not loaded until later, when plots are created.) To view the variables for a particular dataset that has been loaded, click on the dataset name in the list to highlight it, and the variables will be listed in the panel below.

Datasets can be removed by highlighting the name of the dataset in the dataset list and pressing the yellow **minus** button. Note that although the dataset will be removed, the number that was assigned to that dataset will not be reused by VERDI during the current session (unless there had been only one dataset loaded, and it was removed; in that case the next dataset that is loaded will be labeled number 1).

Figure 6-2. Open Dataset File Browser






Figure 6-3. Datasets Pane Displaying Information about a Dataset



6.4 Adding and Removing a Dataset from a Remote File System

VERDI provides users with the ability to select and add variables from datasets on remote file systems. To do this, press the yellow **plus remote** (plus with a diagonal arrow) button at the top of the **Datasets** pane. In the Remote File Access Browser (Figure 6-4) that appears, enter your user name, choose a host from the list, and enter your password, then click **Connect**.

Figure 6-4. Available Hosts in the Remote File Access Browser




6.4.1 Remote File Browser

The top panel displays a listing of the home directory on the remote file system, as shown in Figure 6-5. The current path is displayed in the text box and users can edit this information to change to another directory. An alternate way to navigate between directories is using the middle panel. In the middle panel, double click on a directory name to go into that directory, or click on the “..” at the top of the middle panel to navigate up a directory. As you enter a directory, the contents of the directory will be displayed as a list in the middle panel. Directory names are followed by a “/” symbol, while filenames do not have a “/” symbol after them. View the variables within each file of interest by double clicking on the netCDF filename listed in the middle panel. Note: if the selected file has a format that is not supported by VERDI then the following message will be displayed in the bottom panel: “Not a valid NetCDF file”. For supported netCDF files, VERDI will provide a list of variables that are available within the file in the bottom panel labeled “Select one or more variables”. To select variables from the list, use your mouse to click on a single variable, or use either the Shift key with the mouse to select a contiguous list of variables, or the Control key with the mouse to select a set of individual

variables. Once the variables that you would like VERDI to read are highlighted, click on the **Read** button.

Figure 6-5. Select one or more variables from Remote Dataset




The variables read from the remote dataset will be displayed in the dataset and variable browser in the same way that variables from a local dataset are added and displayed within VERDI. The subsetted local dataset names are identical to the file names on the remote host, except for an additional extension that enumerates how many times the remote files were read and saved locally by VERDI (i.e., filename1, filename2, filename3, etc.), as shown in Figure 6-6. To add additional variables from the same remote dataset, click on the **plus remote** button, and repeat the above procedure. The Remote File Browser retains the login session and the directory that was last accessed by the user, to facilitate ease of accessing remote datasets. VERDI will increment the numerical extension to the dataset name, to allow the user to know that this subset file was created using the same remote dataset, but that the subset file with the new numerical extension may contain a different subset of variables. Note that VERDI does not check to see if the same variable from the same remote dataset has already been read. Also note that subset files read in by VERDI will be saved either to your home directory on your local file system (e.g.,

C:\Documents and Settings\username on a Windows XP machine), or to the location that is specified in the config.properties file using the verdi.tmp.dir setting. Refer to Section 6.4.2 on how to edit and save the config.properties file. The files are saved on your local machine to facilitate project management. To be able to save and then load a project for future use, the files need to be saved on the local machine. To avoid filling up your local file system, regularly inspect the file list in the home or verdi.tmp.dir directory and manually delete unneeded subset files.

Remote datasets can be removed from the dataset list in VERDI using the same procedure as for removing local datasets: highlight the name of the dataset in the dataset list and press the yellow **minus** button. Note that although the dataset will be removed from the dataset list, the number that was assigned to that dataset will not be reused by VERDI during the current session.

Figure 6-6. Remote Dataset Labeled with Number at End of the Filename



6.4.2 Adding Additional Remote Hosts


VERDI contains the RemoteFileUtility and ncvariable programs that enable VERDI to add your I/O API netCDF or WRF netCDF formatted dataset from a remote file system. A gzipped tar file is available in the \$VERDI_HOME directory.

1. The RemoteFileUtility c-shell script and ncvariable binary need to be installed either in /usr/local/bin by the System Administrator, or you can place it in a different location, and specify that location in the configure.properties file located in your \$USER_HOME/verdi/ directory (see section 3.4 for the specific directory location that is used for each platform [Linux, Windows, Mac]). A template for the configure.properties

file called `configure.properties.TEMPLATE` is provided in the distribution under the `$VERDI_HOME` directory (see section 3.4 for information on how to edit the settings).

2. A README file provided with the software contains instructions on how to compile the source code if the binaries provided do not match your operating system.
3. Copy the file `configure.properties.TEMPLATE` to `configure.properties`. Edit the `configure.properties` file in the `$USER_HOME/verdi` directory. Add the name or IP address of the Linux server, preceded by a comma, at the end of the list of machines defined as remote hosts in the `configure.properties` file, as shown in Figure 6-7. You will need to restart VERDI in order for it to recognize a newly added remote host name.

Figure 6-7. Edit `configure.properties` file to add a remote host



```

config.properties - Notepad
File Edit Format View Help
# This file should be put in $USER_HOME/verdi/ subdirectory
# Please use double backslash for windows platform or slash for UNIX like platforms as file
# Please uncomment the following lines and modify them to suit your local settings

# Windows example settings format
verdi.project.home=C:\\Program Files\\VERDI_1.31\\project
verdi.config.home=C:\\Program Files\\VERDI_1.31\\config
verdi.dataset.home=C:\\Program Files\\VERDI_1.31\\data\\model
verdi.script.home=C:\\Program Files\\VERDI_1.31\\data\\scripts

# Linux example settings format
# verdi.project.home=/home/user_a/verdi/proj
# verdi.config.home=/home/user_a/verdi/conf

#verdi.dataset.home=../../data/model
#verdi.script.home=../../data/scripts

# WDT default area file folder
verdi.hucData = ../../data/hucRegion/


# For VERDI to access remote big NetCDF data files
verdi.remote.hosts=emerald.unc.edu,terrae.nesc.epa.gov,vortex.rtpnc.epa.gov
#remote.file.util=

```

6.5 Variables List

The variables list shows all of the variables contained in a loaded dataset (see the example in Figure 6-7). To display a variables list, select the name of the dataset of interest in the **Datasets** pane. Each of the variables in the list can be used to create a formula in the **Formula** pane that can then be used to create plots. VERDI allows the user to automatically add a formula by double clicking on the name of a variable. Double clicking on a variable will automatically create a formula that contains the variable for the loaded dataset and it will become the default formula for making plots. In addition, you may right click on the name of the variable to show a popup menu as shown in Figure 6-8. From this menu you can either add the variable as a formula, or you can to add it into the formula editor so that it can be used to compose more complex formulas. Formulas are described in more detail in Section 7.

Figure 6-8. Right Click on Variable in Dataset Pane




6.6 Time Steps, Layers Panels

The range that is available for the dataset is listed in the Time Steps or Layers Panel in parenthesis next to the label for the panel, e.g. for a dataset that has 5 time steps, the range would be displayed as: Time Steps (1-5). The user can select to use a subset of the full time step range by clicking on the Use Time Range checkbox, and then using the Min and Max spinner controls to set a new minimum or maximum values, for example choosing time step 2 as the minimum time step, and time step 4 as the maximum. When a tile plot is created, it will only display time steps 2-4. Detailed instructions for using the **Time Steps**, **Layers**, and **Domain** panels that you see in Figure 6-7 are discussed in Section 9, “Spatial and Temporal Data Subsetting.”

6.7 Domain Panel

The domain panel contains an Edit button and a Metadata button. Detailed instructions for using the Edit button are provided in Section 9, “Spatial and Temporal Data Subsetting”.

To display the metadata information about a dataset, click on the **Metadata** button in the **Domain** panel. A window containing the metadata will appear (Figure 6-9). Each dataset includes metadata information that is part of the file header. The metadata provided include the map projection information, the number of time steps in the file, the number of columns and rows, and other information.

Figure 6-9. Dataset Metadata Information

6.8 Saving Projects

As noted in Section 5.1.2, lists of datasets and formulas can be saved as “projects” using the Save Project option in the **File** pull-down menu on the VERDI main window. Refer back to that section for discussion on saving new projects and loading existing projects. Note again that the plots created in VERDI are not saved with the project.

7 Working with Formulas


All plots in VERDI are generated from formulas. A formula is used to compare or manipulate variables in one or more gridded datasets. A formula can be as simple as a single variable from one gridded dataset or it can be an equation that uses variable(s) from one or more gridded datasets. Formulas are used to create visualizations that can assist with model performance evaluations, for example, or that help in comparing model results with observations.

7.1 Adding and Removing a Formula

After loading the desired gridded datasets, you can use the variables in them to create formulas. To use a variable to create a simple formula, double click on the name of the variable. This will

add the formula <Variable Name>[<Dataset Number>] to the formula list in the **Formulas** pane—for example, O3[1]. To add a variable to the formula editor window, highlight the variable, **right click** on the variable name in the **Datasets** pane, and select **Add Variable(s) to Formula Editor**. To add all or a subset of variables from the **Dataset** pane to the formula editor window, click on the first variable to highlight it, hold the Shift key down and click at the last variable that you want to include, then right click and select **Add Variables(s)**. The formulas that are highlighted using this method will be added to the formula editor (Figure 7-1).

Figure 7-1. Adding Multiple Variables to Formula Editor



After the variable names are added to the Formula Editor, click on the formula pane and use the cursor and the keyboard to type in the mathematical functions and operators where needed to create a valid formula (see Section 7.2 and Section 16). After the formula has been created in the Formula Editor, click the **Add** button, to place it in the list of formulas available in the **Formula** pane.

To remove a formula from the formulas list, highlight the name in the list and press the yellow **minus** button. Note that removing a formula from the formula list does not remove plots that were created prior to the deletion of the formula.

7.2 Example Formulas

To examine the values of ozone in dataset 1, the formula would be “O3[1]”.

To examine the difference in ozone between datasets 1 and 2, the formula would be “O3[1]-O3[2]”.

To calculate the percent difference in ozone between datasets 1 and 2, the formula would be “(O3[1]-O3[2])*100/(O3[2])”. To identify all cells where the ozone concentration exceeds a certain value, you can use the Boolean operators to “screen out” ranges of your data that are of particular interest. A Boolean expression will evaluate to either True = 1 or False = 0. For example, to plot the cells in which the ozone values in dataset 1 exceed 0.080 ppm, you could use the formula “(O3[1]>0.080)*O3[1]”. In the resulting plot, each cell where O3[1] exceeds 0.080 will show the value of O3[1] for that cell; for all other cells the value shown will be zero.

The notations that can be used in formulas to represent various mathematical functions, and the order of precedence of these functions, are listed in Section 16, “Mathematical Functions.”

7.3 Selecting a Formula for Plotting

Before creating a plot, a formula must be selected. Check to see which formula is highlighted in the **Formula** pane, or look to the right of the plot buttons above the plots area of the main window to see the selected formula. By default, VERDI designates the most recently added formula as the selected formula. To change the selected formula to a different one in the list, click on a formula in the list on the **Formula** pane, and you will then see it displayed as the selected formula above the plots area.

7.4 Saving Formulas

Both formulas and datasets can be saved using the **Save Project** item in the **File** pull-down menu on the VERDI main window. Saving new projects and loading existing projects was discussed in Section 5.1.

7.5 Time Step Range, Layer Range, and Edit Domain

Instructions for using the **Time Steps**, **Layers**, and **Domain** panels that you see in Figure 7-1 are discussed in the next section, “Spatial and Temporal Data Subsetting.”

8 Working with Area Files

8.1 Area File Formats

Area files are defined as shapefiles that contain area features such as watersheds and counties, or any other shapefile that consists of a set of closed polygons.

The shapefile format (ESRI, 1998) consists of four files.

1. The *.shp file contains the actual shape vertices.
2. The *.shx file contains the index data pointing to the structures in the .shp file.
3. The *.dbf file contains the attributes (e.g., gridded concentrations).
4. The *.prj file contains the map projection information used for the gridded concentrations.

8.2 Example Area File

Shapefiles that contain closed polygons are used by VERDI to interpolate gridded data to geographic boundary regions to create Areal Interpolation Plots. Shapefiles containing state, county, or census block, for example, or any other shapefile containing polygon areas may be used in VERDI to calculate and map formulas to the user-selected geographic regions. An example shapefile containing the 8-digit HUC watershed boundary map for the Southeast (Region 3) is provided in the VERDI release under the \$VERDI_HOME/data/HucRegion directory.

Example on-line data archives for these shapefiles include:

<http://datagateway.nrcs.usda.gov>

<http://www2.census.gov/cgi-bin/shapefiles/national-files>

8.3 Adding and Removing an Area File

To load a shapefile, press the yellow **plus** button at the top left corner of the **Areas** pane (Figure 8-1). A file browser (Figure 8-2) allows you to change directories and select a shapefile file for use in VERDI. Click on the shapefile name and click **Next**. The **Open Area** pop-up window will be displayed next which allows you to select the name of the field to read from the file and supply projection information if needed. Use the pull-down menu and click on the Name Field (Figure 8-3) to be used. If a *.prj file is not provided with the dataset, the user is required to specify the projection information. A pull-down menu will prompt the user to select the coordinate system used in the file: either the Geographic (lat/lon) coordinate system or a Projected (x/y) coordinate system (Figure 8-4). If the user selects Projected, an additional pull-down menu asks what type of projection, and a text box allows users to provide the required information to do the projection (Figures 8-5 and 8-6). After the Name Field and the Coordinate System have been specified, select **Finish**. The resulting plot will be in the same projection as the gridded information used in the plot.

8.4 Areas List

The shapefile name(s) will be listed in the top panel of the **Areas** pane, and the name fields for the polygons provided in the shapefile(s) will be listed in the panel underneath (Figure 8-7). The actual model data are not loaded until later, when the Areal Interpolation plots are created. As additional shapefiles are added, the name fields associated with each shapefile are appended to the bottom of the Areas list. Use the scrollbar on the right side of the **Areas** pane to view the additional name fields that are available. To remove a shapefile, click on the name of the shapefile and press the yellow **minus** button at the top left corner of the **Areas** pane.

8.5 Areal Interpolation

When the user selects the Areal Interpolation Plot, the selected formula is remapped over the polygon areas that are listed in the **Areas** pane. To select a subset of the polygon areas, and view the average and total values for selected formulas, see Section 10.3: Areal Interpolation Plot.

Figure 8-1. Areas Pane




Figure 8-2. Open Area File Browser




Figure 8-3. Open Area File: Select Name Field




Figure 8-4. Coordinate System




Figure 8-5. Projection Information




Figure 8-6. Additional Data Fields appear depending on projection selected.

Open Area File: Coordinates

Please select the name field and the coordinate projection to use.

Name Field: PRJ_COV_ID

Coordinate System: Projected (x,y)

Projection Information

Projection: Polar Sterographic Projection

Central Meridian

Ellipsoid Name: Airy


Latitude of Origin

False Easting

False Northing

<Back Next> Finish Cancel

Figure 8-7. Area Name Fields available for Shapefile




9 Spatial and Temporal Data Subsetting

Both the **Dataset** pane and the **Formula** pane include the three panels discussed in Sections 9.1 through 9.3: **Time Steps**, **Layers**, and **Domain**. Section 9.4 then discusses the precedence rules for subsetting data that determine which pane's subsettings (**Dataset** or **Formula**) take priority.

9.1 Specify Time Step Range

Information about the range of time-step values included in a dataset is displayed in the **Time Steps** panel (Figure 9-1). The maximum time-step range that can be used for a dataset or formula is specified in the **Min** and **Max** spinner controls. You can use these controls to select a subset of the available time-step range for plotting. Check the **Use Time Range** box above the spinner controls to tell VERDI to use the time-step range values you have specified when it creates a plot. By default, a plot will initially display data for the minimum time step that was specified in the **Time Steps** panel. The range of the time steps available in the **Time Step** spinner control at the top of the plot will reflect the subset of time steps specified when the **Use Time Range** box is checked. The date and time of that time step are shown below the plot. Subsetting (also called cropping) a dataset's or formula's time-step range will affect any plots made; see Section 9.4 to learn the precedence rules.

Figure 9-1. Specify Time Step Range




9.2 Specify Layer Range

Information on the range of vertical model layers included in a dataset is displayed in the **Layers** panel (Figure 9-2). You can use the **Min** and **Max** spinner controls to select a subset of the available layer data for plotting. Check the **Use Layer Range** box above the spinner controls to tell VERDI to use the layers you have specified. By default, a plot will initially display data for the minimum layer chosen in the **Layers** panel. The range of the layers available in the **Layer** spinner control at the top of the plot will reflect the subset of layers specified when the **Use**

Layer Range box is checked. Subsetting a dataset's or formula's layer range will affect any plots made; see Section 9.4 to learn the precedence rules.

Figure 9-2. Edit Layer Range in Formula Pane



9.3 Specify Domain Range

Datasets contain data for cells over a particular geographic area. In the VERDI program this area is referred to as a “domain.” By default, the entire domain contained in a dataset is used in creating plots. The **Edit Domain** dialog box can be used to select a subset of this domain for plotting. To access the **Edit Domain** dialog box, first use the vertical slide bar to bring the **Domain** panel (located below the **Layers** panel) into view if it is not already visible (Figure 9-3). To select a subset of the domain, press the **Edit** button. The **Edit Domain** dialog box will appear (Figure 9-4). If the area of interest is large, background data such as state and county outlines will be shown on the map. The **magnifying glass** buttons above the map can be used to zoom in and out on the map. Use the **pan** icon to drag the map to a position where the desired area is displayed. To select the desired cells, first press the **Select Region** button. You can then drag a box around the area of interest; selected cells will appear in blue. To clear out the selected area, use the **Clear Region** button. When you are satisfied with the domain subset you have chosen, click the **OK** button. Subsetting a dataset's or formula's domain range will affect any plots made; see Section 8.4 to learn the precedence rules.

Figure 9-3. Using the Slider to View the Domain Panel





Figure 9-4. Edit Domain Dialog Box



9.4 Rules of Precedence for Subsetting Data


The subsetting feature allows the user to combine variables from two or more datasets that may have originally contained differing layer, time step or domain ranges, when a sub-portion of the datasets contains an identical set of layers, time steps and domain range. The user may select a subset of the data available in the dataset so that the range selected is for an identical time step, layer and domain range so that they may be used to create a formula and be displayed in a plot. Because both the **Dataset** pane and the **Formula** pane have the **Time Steps, Layers, and Domain** panels described above, precedence rules were established that determine which pane's subsettings take priority. It is important to understand these rules.

- A subset of data specified in the **Dataset** pane takes precedence over any subset specified in the **Formula** pane. At the time of this release, the range displayed in the **Formula** pane does not get updated when a subset range is selected on the **Datasets** pane. For example, if a dataset has a full time-step range of 0-48, and a time-step range of 2-40 is selected on the **Dataset** pane, then the 0-48 time-step range that is listed for the formula in the **Formula** pane is not applicable. When a plot is then created, the time-step range subset you chose in the **Dataset** pane (2-40) is displayed.

If no subsetting has been done for a particular data type (time steps, layers, or domain) in the **Dataset** pane, then any subsetting done for that parameter in the **Formula** pane will take effect.

- When a subset of data is requested in the **Dataset** pane, this deactivates the ability to further subset the data for this range in the **Formula** pane. For example, if the data are subset in the **Dataset** pane to a layer range of 2-7, and then in the **Formula** pane you attempt to further subset the layer range to 4-5, the further subsetting will be ignored and the plot will be created with a layer range of 2-7.
- When the user wants to create formulas using variables from multiple datasets, it is important to use the **Formula** pane to subset the domain range (if such subsetting is needed). The user should not try to create matching subset domain ranges for multiple datasets using the **Dataset** pane for each dataset, because if all of the subsetted domains do not match exactly, an error will occur when the user attempts to create a formula using variables from those datasets (Figure 9-5). Using the **Formula** pane instead to do the domain subsetting allows the user to select a subset of the domain to be applied for all dataset variables used in the selected formula.

Figure 9-5. Error obtained when incompatible subset domains are created using the Dataset pane



10 Creating Plots


After creating a formula, you are ready to create and view some plots. The available plot types are shown on the buttons at the top of the VERDI main window: fast tile plot, vertical cross section plot, time series plot, time series bar plot, scatter plot, vector plot, and contour plot. All of these are described in this section. Once you have selected (highlighted) a formula in the list of formulas you have created in the **Formula** pane, you generate each plot type by clicking on the appropriate button using your left mouse button. You can also see the selected formula to the right of all of the plot buttons. If additional information is required in order to generate the plot you have requested, a dialog box appears to prompt you for that information.

Each plot contains its own menu bar at the top that has options for configuring and exploring the plot; the four pull-down menus there are **File**, **Configure**, **Controls**, and **Plot**. The options for each of these menus are described in more detail in Section 11, “Configuring Plots Using the Plot Menu Bar.”

10.1 Fast Tile Plot

The **Fast Tile Plot** allows the user to display the time steps and vertical layers contained in a gridded dataset and to display grid cell time aggregate statistics. An example of the **Fast Tile Plot** window is shown in Figure 10-1.

Figure 10-1. Fast Tile Plot



10.1.1 Time Selection and Animation Controls

At the top left of the fast tile plot, the spin control can be used to incrementally change the time step by clicking on the up or down arrow. The top right corner of the plot contains buttons that allow the user to use play, reverse, forward, and pause options to control the animation of the plot. A text box labeled **Slow** allows the user to add a delay between frames by entering a number (delay is in milliseconds); the default delay is 0 milliseconds. (If the text box is not visible, expand the width by clicking with the left mouse button on the edge of the window and dragging to the right.) Enter a number for the delay in the box and then hit **Enter**. A larger plot with multiple map layers would not require the user to add a delay between frames, but a small zoomed-in plot with few map layers will require the user to add at least a 200-millisecond delay between frames, to comfortably view the data. Putting in a larger number will further slow the animation.

10.1.2 Layer Selection

The Layer displayed for the plot can be controlled by clicking on the up or down arrow for the Layer spin control in the top center of the plot.

10.1.3 Grid Cell Time Aggregate Statistics

The pull down menu option labeled **Stats** provides the user the option to display grid cell time-aggregate statistics (e.g., per-cell minimum, maximum, mean, geometric mean, median, first quartile, third quartile, variance, standard deviation, coefficient of variance, range, interquartile range, sum, time step of minimum, time step of maximum, maximum 8-hour average, and hours of noncompliance).

VERDI calculates the grid cell time aggregate statistics as follows: For each cell (i,j,k) in the currently selected domain (independent of neighboring cells), the aggregated statistical value is calculated over the currently selected time steps. In other words, the aggregated statistical value is calculated for a variable for cells $(i,j,k,tmin...tmax)$, with the number of time steps n , where $n=(tmax-tmin+1)$.

- MINIMUM: $\min(\text{var}(i,j,k,tmin), \text{var}(i,j,k,tmin+1), \dots, \text{var}(i,j,k,tmax))$
- MAXIMUM: $\max(\text{var}(i,j,k,tmin), \text{var}(i,j,k,tmin+1), \dots, \text{var}(i,j,k,tmax))$
- MEAN: SUM / n
- GEOMETRIC_MEAN: $((\text{var}(i,j,k,tmin), \text{var}(i,j,k,tmin+1), \dots, \text{var}(i,j,k,tmax)))^{(1/n)}$
- MEDIAN: $\text{middle_value_of}(\text{sorted}\{\text{var}(i,j,k,tmin), \text{var}(i,j,k,tmin+1), \dots, \text{var}(i,j,k,tmax)\})$
- FIRST_QUARTILE: $\text{value_in_first_quarter_of}(\text{sorted}(\text{var}(i,j,k,tmin), \text{var}(i,j,k,tmin+1), \dots, \text{var}(i,j,k,tmax)))$
- THIRD_QUARTILE: $\text{value_in_third_quarter_of}(\text{sorted}(\text{var}(i,j,k,tmin), \text{var}(i,j,k,tmin+1), \dots, \text{var}(i,j,k,tmax)))$
- VARIANCE: $((\text{var}(i,j,k,tmin)-\text{MEAN})^2 + (\text{var}(i,j,k,tmin+1)-\text{MEAN})^2 + \dots + (\text{var}(i,j,k,tmax)-\text{MEAN})^2) / (n - 1)$
- STANDARD_DEVIATION: $\text{VARIANCE}^{0.5}$
- COEFFICIENT_OF_VARIANCE: $\text{STANDARD_DEVIATION} / |\text{MEAN}|$
- RANGE: $\text{MAXIMUM} - \text{MINIMUM}$
- INTERQUARTILE_RANGE: $\text{THIRD_QUARTILE} - \text{FIRST_QUARTILE}$
- SUM: $\text{var}(i,j,k,tmin) + \text{var}(i,j,k,tmin+1) + \dots + \text{var}(i,j,k,tmax)$

- **TIMESTEP_OF_MINIMUM**: 0-based time step when cell contains its minimum value
- **TIMESTEP_OF_MAXIMUM**: 0-based time step when cell contains its maximum value
- **HOURS_OF_NON_COMPLIANCE**: number of time steps that the cell value exceeds a given threshold

$|\{\text{Var}(I,j,k,t(i)) > \text{threshold}\}|$

- **MAXIMUM_8HOUR_MEAN**: $\text{Max}(M_1, M_2, \dots, M_{n-8})$ where $M_i = \text{mean}(\text{var}(i,j,k,t(i)), \text{var}(i,j,k,t(i+1)), \text{var}(i,j,k,t(i+2)), \dots, \text{var}(i,j,k,t(i+8)))$, for $i = 1..n-8$


10.2 Areal Interpolation Plot

The **areal interpolation** plot displays the interpolated value of the selected formula for each polygon in the selected area file. By comparing the colors of the polygons to those shown in the legend, users can see the relative values of the formula for each polygon area. The Areal Interpolation Plot includes several capabilities that are not available for other plot types, so these are described below, rather than in Section 11: Plot Menu Bar.


10.2.1 Option Pull-down Menu Item

The Areal Interpolation Plot Menu contains an **Options** pull-down menu to allow the user to change the map to display either the Area Averages (Figure 10-2), the Area Totals (Figure 10-3), or the value of the formula contained in the Gridded Dataset (uninterpolated) (Figure 10-4). The **Options** pull-down menu may also be used to display **All** area segments that are loaded in the area list, or to display only the area segments that are selected by highlighting the name field from the area list (Figure 10-5).


Figure 10-2. Areal Plot: Area Average



**Figure 10-4. Areal Interpolation Plot:
Show Grid (Gridded Data)**




**Figure 10-5. Areal Interpolation Plot:
Show Selected Areas**



10.2.2 Areal Values for Polygon Segment

To view the area, total value, and average value for a selected polygon segment use the mouse cursor to hover over a polygon on the map. The values are shown at the bottom left of the information panel (Figure 10-6).

Figure 10-6. Areal Values for Polygon Segments



10.2.3 View and Export Areal Plot Data in Spreadsheet Format

To view the average and total interpolation values for selected formulas in a spreadsheet format, **right click** on the Areal Interpolation Plot and select **Area Information** (Figure 10-7). The Area Information Spreadsheet contains four columns: the identification number from the name field for the polygon, the total area, average interpolated value, and total interpolated value (Figure 10-8). At the top of the **Area Information** tab, the user may select **File>Export** to export the data to a spreadsheet file (Figure 10-9). The save pop-up window allows the user to specify with either a text (.txt) or comma-separated-values (*.csv) format, also known as a comma-delimited file (Figure 10-10).

Figure 10-7. Right Click on Area Plot





Figure 10-8. Area Information Spreadsheet

Area Information: DRYOX_N[1] (0, 0)			
Name	Area (km2)	DRYOX_N[1] (kg)	DRYOX_N[1]_A (kg/ha)
3010101	5655.875740826468	2433536.5	4.302669
3010102	4515.625631195322	2046187.5	4.5313487
3010202	1903.3636596603767	966721.5	5.0790167
3010201	4392.830729537164	2160675.8	4.918641
3010204	4105.370007776452	1804585.9	4.395672
3010105	1545.727366164398	704919.7	4.56044
3010103	5278.531687088094	2507917.2	4.7511644
3010106	1534.467680366486	667539.25	4.3502984
3010205	9742.857916457127	3446319.2	3.5372775
3010104	3206.723523436829	1596897.2	4.9798403
3010203	2184.7607501077305	902749.25	4.132028
3040101	6298.539515028009	2538349.5	4.030061
3010107	3373.2908771270318	1293966.2	3.835917
3020102	2276.128379094424	963203.0	4.2317605
3020101	3355.0225950614754	1514861.4	4.5152044
3020201	6172.757287822339	2985992.2	4.837372
3030002	4378.35502573675	2168069.5	4.9517903
3040102	2334.434805271438	1042260.25	4.464722
3050101	6084.9079734726265	2718787.2	4.4680824
3040103	3086.777843056976	1519024.9	4.9210696
3030003	3734.570705962271	1607924.5	4.3055134
3020103	2532.450120517577	901513.06	3.5598452
3020203	2618.741050173038	976491.75	3.7288597
3020104	2928.108448659794	943170.75	3.2210922

Figure 10-9. Export Spreadsheet

Name	Area (km2)	DRYOX_N[2] (kg)	DRYOX_N[2]_A (kg/ha)
1315	5655.875740826468	2433536.5	4.302669
1327	4515.625631195322	2046187.5	4.5313487
1309	1903.3636596603767	966721.5	5.0790167
1323	4392.830729537164	2160675.8	4.918641
1339	4105.370007776452	1804585.9	4.395672
1363	1545.727366164398	704919.7	4.56044
1384	5278.531687088094	2507917.2	4.7511644
1372	1534.467680366486	667539.25	4.3502984
2220	9742.857916457127	3446319.2	3.5372775
1389	3206.723523436829	1596897.2	4.9798403
2222	2184.7607501077305	902749.25	4.132028
1413	6298.539515028009	2538349.5	4.030061
2225	3373.2908771270318	1293966.2	3.835917
1404	2276.128379094424	963203.0	4.2317605
1417	3355.0225950614754	1514861.4	4.5152044
1424	6172.757287822339	2985992.2	4.837372
1440	4378.35502573675	2168069.5	4.9517903
1473	2334.434805271438	1042260.25	4.464722

Figure 10-10. Name and save spreadsheet




10.2.4 Export Areal Plot Data to Shapefiles

At the top of the **Area Information** tab (Figure 10-11), the user may select **File>Export Shape Files** to export the data to a shapefile. In the Save pop-up window (Figure 10-12), input the name in the File Name field, and select file type: Shapefile (*.shp). The data provided in the spreadsheet—name field, total area, average value, total value—are exported to the shapefile. A GIS program such as User-friendly Desktop Internet GIS (uDig; <http://udig.refractive.net/>), an open-source Java program, may be used to view the shapefiles generated by VERDI. The shapefiles are saved as five separate files that must be kept together as part of the ESRI format (*.shp, *.dbf, *.prj, *.shx, and *.fix). There are no units assigned to the data that are saved in the shapefile, so it is important for the user to keep a copy of the comma-delimited text file, or to keep some alternative text file that specifies the units for each data field.

Figure 10-11. Export Shapefile

Area Information: DRYOX_N[2] (0, 0)	Area (km2)	DRYOX_N[2] (kg)	DRYOX_N[2]_A (kg/ha)
1315	5655.875740826468	2433536.5	4.302669
1327	4515.625631195322	2046187.5	4.5319487
1309	1903.3636596603767	966721.5	5.0790167
1323	4392.830729537164	2160675.8	4.918641
1339	4105.370007776452	1804585.9	4.395672
1363	1545.727366164398	704919.7	4.56044
1384	5278.531687088094	2507917.2	4.7511644
1372	1534.467680366486	667539.25	4.3502984
2220	9742.857916457127	3446319.2	3.5372775
1389	3206.723523436829	1596897.2	4.9798403
2222	2184.7607501077305	902749.25	4.132028
1413	6298.539515028009	2538349.5	4.030061
2225	3373.2908771270318	1293966.2	3.835917
1404	2276.128379094424	963203.0	4.2317605
1417	3355.0225950614754	1514861.4	4.5152044
1424	6172.757287822339	2985992.2	4.837372
1440	4378.35502573675	2168069.5	4.9517903
1473	2334.434805271438	1042260.25	4.464722

Figure 10-12. Name and save shapefile



10.3 Vertical Cross Section Plot

The **vertical cross section plot** allows you to show a slice of data (Figure 10-13). A popup dialog box (Figure 10-14) prompts you for information needed to create the plot. You will need to enter either the column to be used (for an x-axis cross section) or the row to be used (for a y-axis cross section) in the plot. The current time step on the plot can be changed using the **Time Step** spinner control above the plot. There is also a **Column** spinner control to change the column number (or row number). The cross-section column number (or row number) is included in the title of the plot.

Figure 10-13. Vertical Cross Section Plot






Figure 10-14. Vertical Cross Section Dialog Box



10.4 Time Series Plot


The **time series plot** shows a line graph with the average values over time (Figure 10-15). The plot is made for the formula's selected domain, layer range, and time-step range. Each time step's data are averaged linearly to produce that time step's data point. The current layer can be changed using the **Layer** spinner control above the plot. The layer value listed in the title is updated when you change the layer.

Figure 10-15. Time Series Plot



10.5 Time Series Bar Plot

The **time series bar plot** shows average values over time in a bar plot format (Figure 10-16) rather than a line format (Figure 10-15). Other than that, the description of this plot type is the same as for the time series line plot (see Section 10.4).

Figure 10-16. Time Series Bar Plot

10.6 Scatter Plot

The **scatter plot** shows the relationship between two formulas using an array of dots (Figure 10-17). The user specifies the formulas using the dialog box that comes up before the plot is displayed (Figure 10-18). The current time step and layer can be adjusted using the spinner controls above the plot. The data from a scatter plot may be exported by selecting the **File** menu option and then selecting Export data. A pop-up window (see Figure 10-19) allows users to specify whether they would like the data for the current layer, or for all layers, and for the current time step, or for all time steps. Specify the time and layer ranges, and then click the **OK** button. A Save pop-up dialog box will appear. Fill in a file name of your choice with a .csv extension, and specify the directory in which you would like to save this file. The CSV file will be comma delimited, and will contain the following columns of data: layer, time, *x*-axis formula, *y*-axis formula.

Figure 10-17. Scatter Plot




Figure 10-18. Scatter Plot Dialog Box





Figure 10-19. Scatter Plot Export Data into a CSV file



10.7 Vector Plot

The **vector plot** shows vector lines representing the vector formed by using two formulas (one for each component of the vector) across a geographic area; one formula represents the horizontal component, the other represents the vertical component (Figure 10-20). The formulas selected as components of the vector must match in domain, layer range, and time-step range. You specify the components of the vector using the dialog box that comes up before the plot is displayed (Figure 10-21). After the plot is displayed, the current time step and layer can be adjusted using the controls above the plot. Note: the Vector Plot currently uses the old Tile Plot option. In a future release, this plot will be updated to use the Fast Tile Plot.

It is also possible to overlay vectors (e.g., wind vectors) on a tile plot. This can be done either from within the vector plot option (discussed here) or from within the tile plot option (discussed in Section 10.4.4). To do this overlay from within the vector plot option, you select a formula for the Tile option in the vector plot dialog box (Figure 10-21) in addition to specifying the formulas

to be used for the horizontal and vertical vector components. See Section 11.4.4 for more information on vector overlays.

Figure 10-20. Vector Plot





Figure 10-21. Vector Plot Dialog Box



10.8 Contour Plot

The **contour plot** shows a 3-D representation of values over a geographic area (Figure 10-22). The current time step and layer can be adjusted using controls above the plot. You can also animate the plot over time using an option in the **Plot** pull-down menu (Figure 10-23). In addition, the contour plots can be rotated in three dimensions to achieve different viewing angles by using the left mouse button to grab and rotate the plot.

Figure 10-22. Contour Plot




Figure 10-23. Contour Plot Menu Options

File	Configure	Controls	Plot
Print	Configure Plot	Show Lat/Lon	Animate Plot
Export As Image	Load Configuration	Show IsoContours	
	Save Configuration		

11 Plot Menu Bar

Each VERDI plot contains its own menu bar that has options specific to that type of plot. As an example, the menu options at the top of a Fast Tile plot include those shown in Figure 11-1. Most options are common to all plots, and function in the same way (unless the option is grayed out) for all plot types, so it is easier to describe the function of these configuration menu options

once, rather than repeat the same information for each type of plot. Only options that are applicable to a particular plot type are enabled; others are grayed out and cannot be selected. Menu options were rearranged and/or added in VERDI 1.3, which resulted in the Plot Menu Bar being significantly different for the Vector Plot and the Fast Tile Plot. Currently, the Vector Plot is based on the original Tile Plot (which was removed in VERDI 1.4). The Areal Plot is based on the Fast Tile Plot. In a future release the vector plot will also be based on the Fast Tile Plot. The Plot menu bars options will be discussed separately.

The items listed in red font in Figure 11-1 are new options supported in the Fast Tile Plot and Areal Plot; the items listed in blue font are features of Vector Plot that, for the Fast Tile and Areal Plots, were moved to a new column labeled **GIS Layers**.

Plot configuration options that are available in VERDI are discussed in this section.

Figure 11-1. Fast Tile and Areal Plot Pull-down Menu Options

File	Configure	Controls	Plot	GIS Layers
Print Export as Image/GIS	Configure Plot Load Configuration Save Configuration	Zoom Probe	Time Series of Probed Cell(s) Time Series Bar of Probed Cell(s) Time Series of Min. Cell(s) Time Series of Max. Cell(s)	Add Map Layers
		Set Row and Column Ranges		Configure GIS Layers
		Show Grid Lines	Animate Plot	Set Current Maps as Plot Default
		Show Lat/Lon	Add Overlay	

The Plot Menu Bar for the Vector Plot is shown in Figure 11.2. **Configure GIS Layers** is supported in the Vector Plot as an option of **Configure>Maps>Configure GIS Layers**. The map option is highlighted in blue font. When the user selects the map menu option, a pull-down menu allows the user to select map layers, configure GIS layers and set current maps as plot default.

Figure 11-2. Vector Plot Pull-down Menu Options

File	Configure	Controls	Plot
Print Export as Image	Configure Plot Load Configuration Save Configuration Maps	Zoom Probe	Time Series of Probed Cell(s) Time Series Bar of Probed Cell(s) Time Series of Min. Cell(s) Time Series of Max. Cell(s)
		Show Lat/Lon	
			Animate Plot
			Add Overlay

11.1 File Menu Options

Options in the **File** menu include printing a plot and exporting a plot as an image. Plots can be saved as PNG, JPEG, BMP, EPS, or TIFF image file formats; SHP, SHX, DBF Shapefile formats (the shapefiles are saved as five separate files that must be kept together (*.shp, *.dbf, *.prj, *.shx, and *.fix)); and ASCII grid (*.asc) formats.

11.2 Configure Menu Option

The **Configure** pull-down menu contains the following options: Configure Plot, Load Configuration, Save Configuration, and Maps.

11.2.1 Configuring Plots

Figures 11-3 through 11-6 show the dialog boxes that appear when you select Configure Plot. The **Configure Plot** dialog box contains four tabbed options: **Titles**, **Color Map**, **Labels**, and **Other**.

- The **Titles** tab (Figure 11-3) allows you to edit title text and select the font type, size, and color for the title and two subtitles of the plot. Titles may be turned on or off by selecting or deselecting the check box for each title. If a check box is unselected, the title text box, font type and size box, and color box are grayed out.
- The **Color Map** tab (Figure 11-4) allows you to select the number of tiles, the palette type to be used, the color interval, the number format, and the option to have a linear or logarithmic scale. As you vary the number of tiles, the palette types that are available to choose from are automatically updated. The palette type options include sequential (similar to what users typically use for PAVE plots), qualitative, and diverging. The **Interval** pull-down menu is set to Automatic by default. The color intervals are automatically calculated based on the Min and Max values of the dataset and the number of tiles. To change the Min or Max value, type a new value into the text box, and then click **Rebuild**. To specify the number format used in the map legend, enter the format in the entry box using the C language's printf() routine's format syntax, and then click **Rebuild** (e.g., for **%1.2E**, a zero in the legend would be printed with the format "0.00E0"; for **%1.2F** the format would be 0.00). To choose a logarithmic scale, select the pull-down menu option and select **Logarithmic**. The start values for each legend bin will be automatically adjusted when the user changes the scale. Click **Apply** to review changes made to the map while the **Configure Plot** dialog is open. Use the **Apply** button as needed to make additional adjustments to the color map, legend range, and/or number of tiles in the range. To use an irregular spacing or to change the spacing between the color tiles, select **Custom** from the **Interval** pull-down menu and change the interval start values in the list at the bottom of the dialog box. Specify the interval start values for each color in the legend and then click **Apply**. If you try to enter a value for an interval that does not fall between the interval start values that are above and below the value that you are changing,

then the value will not be accepted and the number will revert back to the previous value. When you have chosen to create custom intervals, the Min and Max text boxes and the **Rebuild** button are disabled and grayed out, because you are choosing to override automatic calculation of the color interval spacing and instead define the min, max, and number of tiles manually. Note: values above the maximum specified will be colored the same as the color for the maximum range, and similarly, values less than the minimum specified will be colored the same as the color for the minimum range. Once the settings are finalized, click **OK** and the **Configure Plot** dialog will close.

- The **Labels** tab (Figure 11-5) contains options to edit the labels of the Domain Axis (x-axis), the Range Axis (y-axis), Legend, and Footer. VERDI allows the user to select the number of discreet numerical labels shown on plots. For example, it can be difficult to read the numbers when there are more than 13 different colors on a scale. The legend can be improved by reducing the number of tick marks that are labeled (see Figure 11-5). From the Plot menu option, select Configure> Configure Plot. When the Configure Plot window appears, select the Labels Tab, as shown in Figure 11-5. At the top of the Labels Tab are four additional tabs that can be selected: Domain Axis, Range Axis, Legend, and Footer. To edit the number of tick marks that are labeled on the Legend of the plot, select the Legend tab, and there will be a check box labeled Show Tick Labels, and a text box where you can change the number of tick labels that are placed on the plot. After you change the number of tick labels and click on the Apply button, the density of the labels on the plot is increased or decreased accordingly. Once you are satisfied with the number of Tick Labels on the Legend of your plot, then click Apply. If you would like to change the number of tick marks on the Domain Axis, click on the Domain Axis Tab, and you will see the check box labeled Show Tick Labels, and a text box. Change the number in the text box, then Click OK, and repeat this for the Range Axis Tab. Once you are finished customizing the number of Tick Labels for the three different regions of the Plot, click OK, and the Configure Plot Window will close. Figure 11-7 shows an example plot where the number of Tick Labels has been reduced in both the Range Axis and the Legend, but the number of tick labels has not been reduced in the Domain Axis.
- The **Other** tab (Figure 11-6) allows you to enable or disable showing the grid lines, and to edit the vector arrow color and the series color. The edit series color allows the user to specify the colors used to shade the bars for the time series bar plot, or the colors of the lines on the Time Series Plot.

Figure 11-3. Configure Plot, Titles Tab




Figure 11-4. Configure Plot, Color Map Tab




Figure 11-5. Configure Plot, Labels Tab




Figure 11-6. Configure Plot, Other Tab





Figure 11-7. Example Plot with Tick Marks reduced for the Legend and Range Axis



11.2.2 Loading and Saving Configuration

If you have made changes to the configuration of a plot, and would like to save the configuration for future use on other plots, use the **Save Configuration** option from the **Configure** pull-down menu on the plot. It is important to create a file name that indicates the formula name, the dataset, and the type of plot, along with the .cfg extension that indicates that it is a configuration file, so that you will know which plot the configuration file was saved for. An example file name is <FormulaName>_<DatasetFilename>_<PlotType>.cfg, or “O3_CCTM_base_tile.cfg”. This is only an example name; you may use your own naming convention. What is important is not how you name the files, or how you organize the files into directories, but that you remember the datasets and variables to which a specific configuration may be applied. Saved configuration files may also be invoked in batch or command line scripts by setting the parameter configFile; i.e., configFile=C:\\Program Files\\VERDI_1.4.1\\data\\configs\\o3_10bin.cfg.

To load a previously saved plot configuration, first create a plot that is of the same type, and uses the same formula that is used within the configuration file. Then select the **Load Configuration** option from the **Configure** pull-down menu on the plot. An **Open File Dialog** window will allow you to look for the directory in which you saved the configuration file, and to open that file. The plot title, color map, and other plot configuration features will be applied to the plot. Note that it is possible to load a saved configuration file that does not apply to the selected plot,

so before loading a saved plot configuration check carefully to be sure the plot type and formula of the configuration file match those of the plot.

11.3 Controls Menu Options

The **Controls** pull-down menu contains the following options: Zoom, Probe, Set Row and Column Ranges, and Show Lat/Lon.

11.3.1 Zoom Using the Left Mouse Button


To zoom in and enlarge a subdomain of the data, select the **Zoom** option. Then hold down the left mouse button and use the mouse to click on a region of the map and then draw a rectangle around the region of interest. To zoom out click on the map in the right bottom corner using the left mouse button, and while holding down the left mouse button, move the mouse to the upper left corner and then release the left mouse button.

11.3.2 Zoom Using the Right Mouse Button

11.3.2.1 Vector Plot

On a vector plot, right click on the map to see a pop-up window that will allow you to select Zoom In or Zoom Out on either Both Axes, the Domain Axis, or the Range Axis. Select Auto Range>Both Axes to recover the plot of the full domain, or select Auto Range> Domain Axis or Range Axis to zoom out fully along only the domain axis or only the range axis (Figure 11-8).


Figure 11-8. Right Click on Tile Plot to Zoom Out



11.3.2.2 Fast Tile Plot and Areal Plot

To zoom on a fast tile plot or areal plot, use your mouse button to right click on the map in the area of interest. A pop-up window will appear, allowing you to select Zoom In, Zoom Out, or Max Zoom Out to recover the plot of the full domain (Figure 11-9).


Figure 11-9. Right Click on Fast Tile Plot to access Zoom Out Option



11.3.3 Probing Values at Specific Points

To determine the data value at a specific point, select the Probe option under the **Controls** pull-down menu. To probe a single data point, use the mouse to hover the cursor over that grid point on the map; the coordinates of the grid points are shown in the lower right-hand side of the plot in the format (column, row). Once you click on the grid point of interest, the value of the datum at that grid point is displayed in the lower left-hand area of VERDI main window (Figure 11-10).

Figure 11-11. Spreadsheet Showing Probed Values for Region of Interest



11.3.5 Set Data Ranges

The **Controls>Set Row and Column Ranges** menu item will bring up a pop-up window that allows the user to configure the minimum and maximum values used in the row (*x*-axis range) and column (*y*-axis range) (Figure 11-12 and 11-13). Specify the values and then click OK.

Figure 11-12. Select Set Row and Column Ranges






Figure 11-13. Enter Row and Column Values



11.3.6 Showing Latitude and Longitude

To view the latitude and longitude values for a point on the plot, select the Show Lat/Lon option on the **Controls** menu, then hover your cursor over the location for which you would like to know those values. The lat/lon coordinates will be displayed in the lower right-hand side of the window (Figure 11-14). The option to display the lat/lon coordinates may be selected, and works with either the Zoom or the Probe option.


Figure 11-14. Lat/Lon Values Shown in Lower Right of VERDI



11.4 Plot Menu Options

The **Plot** pull-down menu (Figure 11-15) contains the following options: Time Series of Probed Cell(s), Time Series Bar of Probed Cell(s), Time Series of Min. Cell(s), Time Series of Max Cell(s), Animate Plot, and Add Overlay.

Figure 11-15. Plot Menu Options



11.4.1 Time Series Plots

The Time Series of Probed Cell(s) and Time Series Bar of Probed Cell(s) allows the user to select a set of cells, and then produce a time series or time series bar plot of the chosen subset of probed cells. The Time Series of Min.[or Max.] Cell(s) option creates a time series plot using data for the currently selected formula at that formula's domain, layer range, and time step range. The minimum [or maximum] value of that formula over the domain and layer range at that time step is calculated by VERDI and used for each of the time step's data points.

11.4.2 Animate Plots

You can create an animated plot by selecting the Animate Plot option. The Time Series and Time Series Bar Plots do not have an Animate Plot option. The plots that may be animated include: Tile, Fast Tile, Vertical Cross Section, Vector Plot, and Contour Plot. An Animate Plot dialog box (Figure 11-16) will appear, allowing you to save animations either as an animated GIF with a file extension of .gif or as a Quicktime movie with a file extension of .mov. This **Plot** menu option is plot-specific and so does not allow you to animate more than one plot at a time. To animate multiple plots, you will need to use the **Plots** pull-down menu at the top of the VERDI main window; see Section 5.2.2, "Animate Tile Plots."

Figure 11-16. Animate Plot Dialog Box

11.4.3 Add Overlays

11.4.3.1 Observational Data Overlays

It is useful to visually compare the results contained in model output datasets with the data points in observational datasets. You can do this by creating a fast tile plot of the model output and then overlaying observational data points on the plot. The observational dataset needs to be in an I/O API observational data format (see Chapter 13 for more information about how to convert AIRS observational data into this format) or CSV-or tab delimited format observational data.

Sample observational data are provided under the directory \$VERDI_HOME/data/obs to allow the user to create a sample Observational Data Overlay Plot. To begin, load both a model output dataset and an observational dataset. Note that when the observational dataset is loaded in the **Dataset** pane an (obs) label appears to the right of the dataset name in the Dataset pane. When the user double clicks on a variable available from an observational dataset and adds it to the Variable pane, an (obs) label appears to the right of the dataset name in the **Variable** pane. Next, create a formula in the **Formula** pane using a variable from the *model output* dataset. Use this formula to create a fast tile plot. (Note: If you create a formula referencing a variable from an *observational* dataset, this formula will appear in the formula list but it cannot be used to create a plot. If you try to use a formula that contains a variable from an observational dataset, the following error will occur: “Error while evaluating formula: Selected dataset is observational.”)

To view observational data as an overlay on a fast tile plot, select Add Overlay>Observations from the fast tile plot’s **Plot** pull-down menu (Figure 11-15). An **Observation** dialog box (Figure 11-17) will appear containing the variables that are available in the observational dataset. Multiple observational dataset variables can be overlaid on a fast tile plot. Select the observational variable or variables that you would like to overlay on the fast tile plot from the Observation Details list. You then have the option to control the appearance of the symbols that represent the observational data. The stroke size controls the thickness of the line used to draw the symbols, while the shape size controls their diameter. You can use up to six different open-

area shapes—circle, diamond, square, star, sun, and triangle—to distinguish among multiple observational datasets. After you select the variable, and optionally set the stroke size, shape size, and symbol, select **Add Variable** and then **OK** to overlay the observational data on the fast tile plot (Figure 11-17). If you do not specify the size, shape, or symbol, VERDI will use default values. The symbol shape is set by default to a circle. Repeat the process to add multiple variables. To remove the symbols for a variable on an observational data overlay, or to reset their size or shape or stroke thickness, re-open the **Observation** dialog by using Add Overlay>Observations and then click on the observational variable you wish to adjust and then change the stroke size, shape size, or symbol, and/or move it up or down, or remove it, and then click OK. The center of the observational data point corresponds to the lat/lon value that is provided in the I/O API observational data file. Figure 11-18 shows a fast tile plot with grid lines drawn illustrating that when more than one observational data point are located at the same location, they are placed on top of one another, so the user may wish to select different symbols for each dataset, with the largest symbol on the bottom, and the smallest symbol on the top.

Figure 11-17. Fast Tile Plot Observation Dialog





Figure 11-18. Fast Tile Plot with Multiple Observational Data Overlays with Grid Lines




11.4.3.2 Vector Overlays

Users have two options to display vectors (e.g., wind vectors) on a plot. One option is to select the vector plot type, using the procedure described in Section 9.7 to display the vectors on a map. The other option is to display the vectors as an overlay on a fast tile plot, as described below.

To add a vector overlay to a fast tile plot, select the Add Overlay>Vectors option from the fast tile plot's **Plot** pull-down menu (Figure 11-14). The Vector Overlay dialog box (Figure 11-19) asks you to select the formula for the horizontal component and the formula for the vertical component. The formulas listed in the Vector Overlay dialog box are obtained from the formula list in the **Formula** pane. If the formula you would like to use is not listed in the Vector Overlay dialog box, check to be sure that you have loaded the dataset that contains the variable of interest (for example, UWIND), and that you have created a formula UWIND[x], where x is the dataset number associated with the dataset that contains UWIND. Once you have selected the two components, click **OK**, and the vector overlays will be displayed on the plot. Currently, vectors are plotted in the center of the grid cell. UWIND and VWIND are typically obtained from


METCRO3D, which are defined at dot points or cell corners. Plotting the wind vector at their calculated locations and adjusting the length of the wind vector based on the magnitude of the wind speed will be added to the Fast Tile Plot in a future release.

Figure 11-19. Vector Overlay Dialog Box



An example of an ozone concentration fast tile plot with wind vector overlays is shown in Figure 11-20. By default, the vectors are all given the same length. The thickness of the line width used to draw the vector indicates the magnitude of the vector; a larger-magnitude vector is drawn with a thick line, a smaller-magnitude vector with a thinner line. At this time there is no user control over how the vectors are displayed, and there is no option to remove the vectors from a tile plot.


Figure 11-20. Wind Vector Overlay on an Ozone Fast Tile Plot



11.5 GIS Layer Options (Fast Tile Plot)

The **GIS Layers** pull-down menu (Figure 11-21) contains the following options: Add Map Layers, Configure GIS Layers, and Set Current Maps As Plot Default.

Figure 11-21. Plot Menu Options




11.5.1 Add Map Layers

The **Add Maps Layers** option in the **GIS Layers** pull-down menu is used to add maps to a Fast Tile Plot or Areal Interpolation Plot (Figure 11-22).

A selection of default maps—including World, North America, USA States, USA Counties, HUCs, Rivers, and Roads—can be selected or deselected by clicking with the left mouse button on one of these map names. This will cause a check button to appear or disappear next to the chosen map name, and the selected map to appear on the plot.

Figure 11-22. Add Map Layers



The fast tile and areal interpolation plots use a new format for all maps and GIS layers, called the bin format, to improve the speed of displaying the map layers. A shape2bin program that runs on Linux and Windows platforms has been provided with the VERDI distribution to allow users to convert new map shapefiles to the bin format for the fast tile plot. The shape2bin tool requires an unprojected shapefile as input. For example, an error will occur if the user tries to convert a lambert projected shapefile.

Linux/Mac:


- extract the shape2bin.zip that is located under \$VERDI_HOME/VERDI_1.4.1/ directory using: unzip shape2bin.zip
- cd shape2bin

- Several Linux binary executables are provided in with the code under the bin directory. A makeit script is provided that documents the compiler flags and options used to build the executables.
- Edit the runit script to specify DATA_DIR as the directory where your shapefiles are located. Run the script using the syntax: ./runit The bin files will be written to the same directory as where the shapefiles are located. After the script has run, copy the new bin file from the DATA_DIR directory to the bin map directory: \$VERDI_HOME/Verdi_1.4.1/plugins/bootstrap/data, as this is where VERDI looks for the bin format files. Several shapefiles and their converted bin files are provided under the bin map directory.

Windows

- Extract the win_shape2bin.zip file provided under the \$VERDI_HOME/verdi_1.4.1 directory by double clicking on the file.
- Copy the two files cygwin1.dll and shape2bin.exe to the bin map directory: C:\Program Files\VERDI_1.4.1\plugins\bootstrap\data
- Place the shapefile(s) that you would like to convert into the bin map directory
- Start a command line prompt by using Run and type in cmd
- cd C:\Program Files\VERDI_1.4.1\plugins\bootstrap\data
- type the command shape2bin, and it will provide the format that the user should use to convert a shape file to a bin file (see Figure 11-23)

Figure 11-23. shape2bin command usage



```
C:\Windows\system32\cmd.exe

C:\Program Files\VERDI_1.4\plugins\bootstrap\data>shape2bin

shape2bin - Convert Shapefile *.shp to map*.bin file.
usage:  shape2bin file.shp > map_file.bin
example: shape2bin NCA.shp > map_estuaries.bin
head -4 map_estuaries.bin


Email questions and comments to: plessel.todd@epa.gov

C:\Program Files\VERDI_1.4\plugins\bootstrap\data>
```

11.5.2 Configure GIS Layers (Fast Tile Plot)

To show an additional map on the plot, select the **Configure GIS Layers** option in the **GIS Layers** pull-down menu. When you click on this item, a dialog box titled Manage Layers gives you the following options: Add Layer, Move Up, Move Down, Remove Layer, and Edit Layer (Figure 11-24).

Figure 11-24. Manage Layers Dialog Box



- When you select Add Layer, an **Add Layer** pop-up window (Figure 11-25) prompts you to select a map file to import into the base map. Navigate to bootstrap/data directory, or to a directory where shape2bin was used to convert a shapefile and select a map file with the .bin extension and click next. The **Edit Layer** pop-up window allows you to edit the layer style (Figure 11-26), or you can use the default line color and thickness. The outline color of the map layer can be changed to help distinguish between map layers by clicking on the box next to outline color and selecting from the color palette (Figure 11-26). The outline transparency or thickness can be changed by using spin controls to change the values. Once the layer style editing is done, Click **Finish**, and the new map name will appear in the list on the **Manage Layer** pop-up window. After the layer you have added and edited is listed in the Manage Layers dialog box, click OK to have the layer added to the plot. If you add multiple layers to the list in this dialog box, the one at the top of the list is the top layer shown on the plot.
- To rearrange the order in which the GIS layers are displayed on the plot, select a layer in the Manage Layers dialog box, and then select Move Up or Move Down, and then click OK to reposition the order of that layer within the list. If the layers that you are selecting are boundaries and were created to have a transparent fill, then rearranging the order of the layers will not change the look of the boundaries on the plot.

- To remove a GIS layer from the plot, select that layer in the list, then select Remove Layer, then click OK to remove it.
- To edit a GIS layer, select the layer from the list under Manage Layers and then select Edit Layer. The **Edit Layer** pop-up window will allow you to select the map outline color, transparency, and thickness (see Figure 11-26).

Figure 11-25. Add Layer Pop-up Window





Figure 11-26. Edit Layer Pop-up Window



11.5.3 Set Current Maps as Default Location

This option is currently grayed out. It will be supported in a future release to allow a user to specify and save the maps loaded by default to a configuration file.

12 Supported Grid and Coordinate Systems (Map Projections)

VERDI makes calls to the netCDF Java library to obtain the grid and coordinate system information about the data directly from the model data input files when the input data files are self-describing (CMAQ, SMOKE, WRF netCDF format files).

12.1 I/O API-formatted Data

For I/O API files, support for Lambert conformal conic (LCC) map projection, Universal Transverse Mercator (UTM) map projection, and polar stereographic map projection was added in VERDI 1.1., and Mercator projection in VERDI 1.2. The grid projections listed on the following website are supported, although not all have been tested:

<http://www.baronams.com/products/ioapi/GRIDS.html>

Users are encouraged to provide small input datasets as attachments to emails to the m3user listserv, or via ftp, for testing and to facilitate future development efforts. Figures 12-1 through 12-4 shows example plots generated for a dataset with an LCC, polar stereographic, Mercator, and UTM map projections, respectively.

Figure 12-1. Lambert Conformal Conic Map Projection Example Plot




Figure 12-2. Polar Stereographic Map Projection Example Plot




Figure 12-3. Mercator Map Projection Example Plot





Figure 12-4. UTM Map Projection Example Plot



12.2 CAMx Gridded Data

The netCDF-java v4.1 library used in the VERDI 1.4.1 release includes support for CAMx UAM-IV binary files, using a pre-set default projection. CAMx or UAM binary files contain information about the x and y offsets from the center of the projection in meters, but do not contain information about the projection. The projection information is available in separate diagnostic files, which are part of the CAMx output along with the UAM binaries (Figure 12-5)

Figure 12-5. Example CAMx diagnostic text file

```

*****
                        CAMx
*****

CAMx

Simulation start time/date :      0.      060428      06118
Simulation end time/date   :      0.      060429      06119
Time zone                  :          0
Max timestep (min)        :      15.
Met Input interval (min)  :      60.
Emiss Input interval (min):      60.
Output interval (min)     :      60.
Grid Projection Type      : LAMBERT
LAMBERT: center lon/lat   :     -97.000    40.000
LAMBERT: true latitudes   :      45.000    33.000
Master Grid X/Y Origin    :    -2736.000 -2088.000
Master Grid cell size     :      36.000    36.000
Master Grid NCOL NROW NLAY :          148         112         19
    
```

The netCDF-java v4.1 library writes the default projection information to a text file in the directory where the CAMx binary (UAM-IV) file is located. This allows the user to review and edit the projection information to make it consistent with the projection specified in the CAMx diagnostic text files. The definitions of the projection parameters used in the camxproj.txt file are defined using Models-3 I/O API format, <http://www.baronams.com/products/ioapi/GRIDS.html>. The user must edit the camxproj.txt file to match the grid description information provided in the corresponding camx.diag file. Figure 12-6 shows the definition for the grid projection parameters for a Lambert projection.

Figure 12-6. Models-3 I/O API Map Projection Parameters for Lambert

```


Lambert Conformal Conic:
GDTYP = 2
P_ALP <= P_BET are the two latitudes which determine the projection cone;
P_GAM is the central meridian.
(X_CENT,Y_CENT) are the lat-lon coordinates for the center (0,0) of the
Cartesian coordinate system. Coordinate units are meters.
    
```

Figure 12-7 shows the values of the camxproj.txt once it was edited to match the values of the camx.diag file (Figure 12-4) using the definitions of the Models-3 grid parameters (Figure 12-5). Figure 12-8 shows the resulting Fast Tile Plot of the CAMx sample dataset.

Figure 12-7. Sample Projection File: camxproj.txt

```
# Projection parameters are based on IOAPI. For details, see  
www.baronams.com/products/ioapi/GRIDS.html  
GDTYP=2  
P_ALP=33.0  
P_BET=45.0  
P_GAM=-97.0  
XCENT=-97.0  
YCENT=40.0
```

Figure 12-8. CAMx Example Plot



13 I/O API Utilities, Data Conversion Programs, and Libraries

As discussed in Section 6.1, there are routines available to convert gridded input data to I/O API format or new code can be written and contributed to VERDI for use by the community. The I/O API routines that have been written to convert data into this format are discussed in this section. If you are unable to use the available routines to convert your data and have a gridded dataset that VERDI is unable to read, please submit a bugzilla bug or enhancement request with a description of the dataset, and attach a small example dataset for use in development and testing.

The I/O API Interface contains an extensive set of utility routines. There are example conversion programs to convert data from different data formats into the I/O API format. The I/O API Utilities are command line programs that are easy to script for automating analysis and post processing. An example of an I/O API Utility that may be useful to VERDI users is m3merge. This utility merges selected variables from a set of input files for a specified time period, and writes them to a single output file, with optional variable-renaming in the process. Another utility that you may find useful is m3extract. This program allows you to extract a few species from a large file and save them to a smaller file on your local computer so you can explore them using VERDI. The I/O API Related Programs and Examples can be found at the following web site: <http://www.baronams.com/products/ioapi/AA.html#tools>.

Airs2m3 is an example of a data conversion program that converts the standard AIRS AMP350 observational data format to the I/O API format. The airs2m3 program requires the following inputs:

- The input AIRS AMP350 print format file name.
- The time zone conversion file (provided with the obs2api program - tzt.dat).
- Additional hour shift variable. The AIRS data are hourly averaged, and a 00 time flag represents the hour 00-01. You may wish to represent that data segment by the ending hour. In that case, a 1 should be entered here.
- Starting year, month, day, hour (GMT) (e.g., 1997 07 10 12).
- Ending year, month, day, hour (GMT) (e.g., 1997 07 16 12).
- Name of output variable (8 characters max) (e.g., O3_OBS).

14 Contributing to VERDI Development

If you have made an improvement to the development of VERDI source code or documentation, please consider contributing it back to the community.

Instructions on how to set up the Eclipse Development Environment on Windows, and for running and building VERDI within Eclipse are available on www.verdi-tool.org. If you are doing a substantial amount of software development on VERDI, you should become a member of the VERDI project on SourceForge and submit your code updates through the VERDI subversion repository. You may submit a request to become a member of the VERDI project by

submitting a Bugzilla request (see below). The SourceForge web site for VERDI is <http://sourceforge.net/projects/verdi/>.

Once your code has been reviewed by the existing team of developers for VERDI, you will be added to the developer list. Contributions to the code will be tested by the VERDI developers and will be included along with the documentation about these contributions in future VERDI releases. Note that anything you contribute must have the same license as the rest of VERDI, i.e. GPL.

The m3user listserv can be used to query known errors, bugs, suggested enhancements, or submitted code contributions using the following website: <http://lists.unc.edu/read/search/?forum=m3user>. First, check to see if your issue is already listed as a bug or request for enhancement. If you do not see an entry that matches, please submit a new request to join the m3user listserv using the following website: <http://www.cmascenter.org/help/listserves.cfm#m3user> and sending an email to the listserv. Use the m3user listserv to notify the VERDI community about improvements to VERDI that you would like to contribute.

15 Known Bugs

As discussed in Section 1.4, you are encouraged to use the VERDI FAQ <http://www.cmascenter.org/help/faq.cfm> and m3user listserv <http://lists.unc.edu/read/?forum=m3user> for searching questions and answers, bug reports, and suggestions. Users are also encouraged to search the CMAS bug-tracking website using: <http://bugz.unc.edu/query.cgi?product=VERDI>. After a bug is verified by CMAS staff, then they will enter information about the bug or feature enhancement request to Bugzilla <http://bugz.unc.edu>.

16 Mathematical Functions

All VERDI visualizations are the result of a formula evaluation. Formulas operate on the variables provided by the datasets. The simplest valid formula consists of a single variable; for example, "O3[1]." Using infix notation, more complicated formulas can be constructed using the following mathematical operators and functions. (Note that the documentation below derives from the equivalent documentation for the Package for Analysis and Visualization of Environmental data [PAVE], which is available at http://www.ie.unc.edu/cempd/EDSS/pave_doc/EntirePaveManual.html.) N

Note that the Batch Script method does not support all of the mathematical functions that are supported within the VERDI GUI and/or the command line script options.

Listed in order of precedence, the functions and operators are:

1. abs, sqr, sqrt, exp, log, ln, sin, cos, tan, sind, cosd, tand, mean, sum, min, max
2. ** (power)
3. /, *
4. +, -
5. <, <=, >, >=
6. ==, !=
7. &&
8. ||

VERDI also supports the following constants:

1. E.....2.7182818284590452354
2. PI.....3.14159265358979323846
3. NROWSNumber of rows in the formula's currently selected domain
4. NCOLSNumber of columns in the formula's currently selected domain
5. NLEVELS.....Number of levels in the formula's currently selected domain

Unary Functions

Unary functions are passed a single argument. Depending on the argument and the function type, the function will return a single value or a matrix of data by performing the function on each cell of the arguments array. For example:

- The function sqrt(4) will return 2.0.
- The function sqrt(O3[1]) will return a matrix containing the square root of each value in the O3[1] variable's array.

The following functions will return a matrix when passed a dataset variable:

1. **abs**.....Returns the absolute value of the argument
2. **sqrt**.....Returns the square root of the argument.
3. **sqr**Returns the square of the argument.
4. **log**Returns the base 10 logarithm of the argument.
5. **exp**.....Returns Euler's number raised the power of the argument.
6. **ln**Returns the natural logarithm of the argument.
7. **sin**.....Returns the sine of the argument. The argument is in **radians**.
8. **cos**Returns the cosine of the argument. The argument is in **radians**.
9. **tan**Returns the tangent of the argument. The argument is in **radians**.
10. **sind**Returns the sine of the argument. The argument is in **degrees**.
11. **cosd**Returns the cosine of the argument. The argument is in **degrees**.
12. **tand**.....Returns the tangent of the argument. The argument is in **degrees**.

The following functions will return a single number in all cases when passed a dataset variable:

1. **mean** Average cell value for all cells in currently selected domain.
2. **sum** Sum of all cell values in currently selected domain.
3. **min** For each cell (i,j,k) in the currently selected domain, this calculates the minimum value for that cell over the currently selected time steps. In other words, the minimum value in cells $(i,j,k,tmin..tmax)$.
4. **max** For each cell (i,j,k) in the currently selected domain, this calculates the maximum value for that cell over the currently selected time steps. In other words, the maximum value in cells $(i,j,k,tmin..tmax)$.

Binary Operators

Binary operators are not passed a value but operate on the operands to their left and right. Typically, they will return a matrix of data by performing the operation on each cell of the operand's arrays. If both of the operands are single numbers then these binary operators will return a single number. For example:

- $O3[1] * 2$ multiplies each item in the $O3[1]$ array by 2 and returns the result.
- $O3[1] * O3[3]$ multiplies each item in the $O3[1]$ array by the corresponding item in the $O3[3]$ array and returns the result. (Note that this assumes that the arrays are of equivalent shape.)
- $3 * 2$ simply multiplies 3 by 2.

The binary operators:

1. **+**Returns the sum of the operands
2. **-**Returns the difference of the operands
3. *****Returns the product of the operands
4. **/**Returns the ratio of the operands
5. ******Returns the left operand raised to the power of the right operand.

Boolean binary operators return either 1 or 0 in each cell of the resulting matrix. If the operands are single numbers, then a single 1 or 0 is returned. The Boolean binary operators:

1. **<**Returns 1 if the left operand is less than the right operand, else 0.
2. **<=**Returns 1 if the left operand is less than or equal to the right operand, else 0.
3. **>**Returns 1 if the left operand is greater than the right operand, else 0.
4. **>=**Returns 1 if the left operand is greater than or equal to the right operand, else 0.
5. **!=**Returns 1 if the left operand is not equal to the right operand, else 0.
6. **==**Returns 1 if the left operand is equal to the right operand, else 0.
7. **&&**Returns 1 if both operands are non-zero, else 0.

8. ||Returns 1 if either operand is non-zero, else 0.


Time Step Index

A time step index can be specified after a variable name. For example, “O3[1]:0” is the value of the O3[1] variable at the first time step.

17 VERDI Batch Script Editor


To open the Script Editor, use File>View Script Editor, as shown in Figure 17-1. Prior running a batch script, remove all datasets from the dataset list. To remove a dataset, click on each dataset in the dataset panel and press the yellow minus button.

Figure 17-1. File: View Script Editor



An **Open** pop-up window will be displayed, click on a sample script file in the VERDI_1.4.1/data/scripts directory (Figure 17-2).

Figure 17-2. Open Pop-up Window



After you select a script file and click Open in the Open pop-up window, the Script Editor window (Figures 17-3 and 17-4) will appear in the right hand side of VERDI. The Script Editor allows you to edit, save, and run batch scripts within VERDI. The Batch Scripting Language used for the VERDI Script Editor is described in the header of the sample text format script files (Figure 17-3).

Figure 17-3. Top of Sample Script File – VERDI_1.4.1/data/scripts/file_patterns.txt

```
#####
# NOTE: Batch Scripting Language #
# #
# * All parameter/value pairs should be inside one of the two blocks -- #
# <Global/> or <Task/> #
# * Number of blocks is not limited #
# * Only one <Global/> block is recommended. <Global/> blocks should #
# contains different items if use multiple <Global/> blocks #
# * Parameter values in <Task/> blocks will override those in <Global/> #
# * Currently supported parameters (keys, case insensitive): #
# configFile -- configuration file full path #
# f -- dataset file path/name #
# dir -- dataset file folder #
# pattern -- dataset file name pattern #
# gtype -- plot type (tile, line, bar, vector) #
# vector -- vector plot variables #
# vectorTile -- vector plot variables #
# s -- variable name #
# ts -- time step #
# titleString -- plot title #
# subTitle1 -- plot subtitle one #
# subTitle2 -- plot subtitle two #
# saveImage -- image file type (png, jpeg, eps, etc.) #
# imageFile -- image file path/name #
# imageDir -- image file folder #
# drawGridLines -- draw grid lines on the tile plot if 'yes' #
# imageWidth -- image width #
# imageHeight -- image height #
# unitString -- units #
# #
# Author: IE, UNC at Chapel Hill #
# Date: 4/30/2013 #
# Version: 1 #
#####
```

Figure 17-4. Bottom of Sample Script File – VERDI_1.4.1/data/scripts/tile_patterns.txt

```
<Global>
dir=../verdi_dist/data/model
pattern=*CCTM46*
s=03[1]
saveImage=jpeg
imageDir=../verdi_dist/data/plots
subTitle1="Test SubTitle 1"
subTitle2="Test SubTitle 2"
</Global>


<Task>
gtype=tile
imageFile=03_tile
</Task>

<Task>
gtype=line
</Task>
```

As shown in Figures 17-3 and 17-4, the Batch Script File format consists of two blocks, a Global block and a Task Block. The Global block allows a user to specify a set of parameters (such as the file and directory names) on which all other tasks will be performed. In this block, the user can specify any parameters that will be used to run any other tasks. If in any other Task block, the same parameters are specified with different values, these values will over-write the values specified in the Global block. One Global Block is used to specify the common parameters shared by all Task blocks, and multiple task blocks can be defined, to specify the type of batch operations that will be performed, such as defining formulas and creating plots

Prior to running a batch script within the Script Editor, all datasets must be unloaded. If they are not, a pop-up warning message will appear (Figure 17-5) requesting that all datasets be unloaded prior to running a batch script in the script editor.

Figure 17-5. Close Dataset(s) Warning Message



The multifiles.txt sample script that is provided as part of the VERDI 1.4.1 release demonstrates how to create a tile plot that uses a mathematical combination of variables, an excerpt of which is shown here:

```
<Task>
dir=D:\\verdi-dist2\\data\\model
f=copy.36k.O3MAX
f=CCTM46_P16.baseO2a.36k.O3MAX
f=another.36k.O3MAX
s=O3[1]-O3[2]+O3[3]*2
gtype=tile
saveImage=jpeg
imageDir=D:\\verdi-dist2
imageFile=three_components_36k.O3MAX
</Task>
```

The above task specifies the name of three input files. The input files are assigned a number based on the order that they are specified.

```
[1]=Copy.36k.O3MAX
[2]=CCTM46_P16.baseO2a.36k.O3MAX
[3]=another.36k.O3MAX
```

`s=O3[1]-O3[2]+O3[3]*2` defines a formula that uses variables from the three filenames

This formula takes ozone in file 1 and subtracts the ozone in file 2 and adds two times the ozone in file 3.

The type of plot is specified as a tile plot by setting the parameter `gtype` to `tile`; i.e., `gtype=tile`.


The image file format is specified by setting the parameter `saveImage` to `jpeg`; i.e., `saveImage=jpeg`.

The output directory where the images will be stored is specified by setting the parameter `imageDir`; i.e., `imageDir=D:\\verdi-dis2`.

The image file name is specified by setting the parameter `imageFile`; `imageFile=three_components_36k.O3MAX`.

Use the left mouse button to highlight the task that you would like to run and then click **Run** in the Script Editor window, a pop-up window will appear that indicates the task ran successfully (Figure 17-6). In the example shown in Figure 17-6, the title and sub-title were obtained from the definition in the global block. Aspects of the plot defined in the global block are used for multiple tasks and are applied even if only a highlighted task is run.

Figure 17-6. Highlight Text to Select Task and Click Run



If the user selects Run without highlighting a Text Block, then the entire batch script will be run, and the plots generated. To edit the batch script, highlight a segment that you would like to copy and use `^C` to copy the text and then click in an area where you want to paste the text and use `^V` to insert the copied text. Test your changes to the script by highlighting the text block and click run, but remember to click Save or Save As... to save the edits that you have made prior to exiting the Script Editor. A successful script run will result in a pop-up window reporting that the run was completed, as shown in Figure 17-7.

After saving the script file (ex. C:\verdi-script\myscript.txt), one can run the batch script directly from command lines without invoking the VERDI GUI windows. On Windows system, bring up a command line window and run this command after changing directory to where the run.bat file locates:

```
>run.bat -batch C:\verdi-script\myscript.txt
```

On Linux/Mac platforms, change directory to where the Verdi.sh locates and run this command (assuming your script file myscript.txt is saved in /home/user/verdi-script directory):

```
$/verdi.sh -batch /home/user/verdi-script/myscript.txt
```

(Note: the full path to the batch script must be specified, neglecting to provide the full path along with the batch script name, will generate the following error: No such file or directory). The batch script usage (see Figure 17-3) will also be displayed from the command line after typing the following command:


(Windows)

```
>run.bat -batch
```

(Linux/Mac)


```
$/verdi.sh -batch
```

Figure 17-7 Successful Batch Script Run Message




If the user has specified an incorrect path, or incorrect filename for the input dataset, then a series of error messages will appear, starting with the message shown in Figure 17-8.

Figure 17-8. Unsuccessful Batch Script Run Message: File not found



In VERDI version 1.4 the VERDI Batch Editor checks to see if the path specified by the user as the imageDir exists, and if the directory does not exist, will give the error message “java.io.FileNotFoundException: with the path and filename listed” followed by a message “(No such file or directory).” This allows you to verify that the path and filename that you used were correct. The directory specified as the image directory must exist or be created by the user prior to running the batch command. Double click on the file in the imageDir directory to load and view the image file in your default visualization software. Figure 17-9 illustrates the tile plot image that was generated by running the highlighted text block.

Figure 17-9. Plot Image Generated by Task Block



17.1 Specify hour/time step formula in batch script mode

In VERDI 1.4 the Script Editor allows the user to specify the timestep using the format:

VARIABLE[dataset number]:timestep.

The following example shows the batch script notation used to specify an hour/time step formula, such as reading O3[1]:17 for hour 17 from a given file in scripting mode (see Figure 17-10).

The batch script can be used to generate plots of a specific hour or time step using the formula

```
s=Variable[dataset#]:hour
```

for example:


```
s=O3[1]:17 to plot the Temperature in first dataset for hour 17
```

Batch Script Example:

```
<Global>
dir=$LOCAL_DIR/verdi_1.4/data/model/
imageDir=$LOCAL_DIR/verdi_1.4/data/images
saveImage=jpeg
</Global>

<Task>
gtype=tile
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile= CCTM46_P16.baseO2a.36k.O3MAX.tstep.17
s=O3[1]:17
</Task>
```

Figure 17-10. Fast Tile Plot of Ozone at Time step 17, Layer 1



17.2 Mathematical function capability in batch script mode

This update provides the user the ability to perform mathematical functions in VERDI using the scripting mode. For example, Find maximum over all time steps at each grid cells.

The batch script can be used to generate plots for each mathematical function by using the task block to define each function. The notation used within the task block is:

```
s=Formula(Variable[dataset#])
```

For example:

```
s=max(O3[1]) to plot the Maximum value over all timesteps for each grid cell in the domain.
```

```
s=min(O3[1]) to plot the Minimum value over all timesteps for each grid cell
```

```
s=mean(O3[1]) to plot the Mean value over all timesteps for each grid cell
```

```
s=sum(O3[1]) to plot the Sum of the variable over all timesteps for each grid cell
```


The Mathematical functions will operate over all time steps at each grid cell. Examples for the batch script notation and the images produced are provided in the sections below.

17.2.1 Batch Script Example: Maximum Ozone – layer 1 (Figure 17-11)

```
<Global>
dir=$LOCAL_DIR/verdi_1.4/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_1.4/data/images
saveImage=jpeg
</Global>

<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepmax.layer1
s=max(O3[1])
</Task>
```

Figure 17-11. Fast Tile Plot of Maximum Air Temperature (aggregated over 25 time steps)




17.2.2 Batch Script Example : Minimum Ozone – layer 1 (Figure 17-12)

```
<Global>
dir=$LOCAL_DIR/verdi_1.4/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_1.4/data/images
saveImage=jpeg
</Global>

<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
```

```
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepmin.layer1
s=min(O3[1])
</Task>
```


Figure 17-12. Fast Tile Plot of Minimum Ozone (aggregated over 25 time steps)



17.2.3 Batch Script Example : Mean of Ozone – layer 1 (Figure 17-13)

```
<Global>
dir=$LOCAL_DIR/verdi_1.4/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_1.4/data/images
saveImage=jpeg
</Global>
<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepmean.layer1
s=mean(O3[1])
</Task>
```

Figure 17-13. Fast Tile Plot of Mean Ozone (aggregated over 25 time steps)




17.2.4 Batch Script Example : Sum of Ozone – layer 1 (Figure 17-14)

```

<Global>
dir=$LOCAL_DIR/verdi_1.4/data/model/
gtype=tile
imageDir=$LOCAL_DIR/verdi_1.4/data/images
saveImage=jpeg
</Global>
<Task>
f= CCTM46_P16.baseO2a.36k.O3MAX
imageFile=CCTM46_P16.baseO2a.36k.O3MAX.tstepsum.layer1
s=sum(O3[1])
</Task>
    
```

Figure 17-14. Fast Tile Plot of the Sum of Ozone (aggregated over 25 time steps)



18 Command Line Scripting

The commands described in this section can be executed from the command line through either command line arguments or Windows batch files. In Linux, you can edit the verdi.sh script, adding the command options at the end of the last line of the script. If you are using Windows, edit the run.bat script, again adding the command options at the end of the last line, and submitting the script at the windows command line. An example syntax for all commands follows the format

<command> <command options> \

where the “\” at the end of the command is optional.

18.1 Example Command Line Script for Linux Users

Set an environment variable \$VERDI_HOME by using

```
setenv VERDI_HOME /home/a_username/VERDI_1.4.1
```

Where a_username is your username.

The following script options will read in the file as the first dataset, select O3[1] as the formula from dataset 1, and create a tile plot of the O3[1].

```
./verdi.sh -f "$VERDI_HOME/data/model/CCTM46_P16.baseO2a.36k.O3MAX -s O3[1] -  
gtype tile
```

Example script file (Note that quotes (as shown highlighted in red) may be needed around the entire list of parameters" :


```
#!/bin/csh -f  
  
#### 8hO3 Daily Max Plot  
setenv DIR /home/training/verdi_1.4/data/OBS  
../../verdi.sh \  
"-f $DIR/ACONC_O3_8hr.dmax \  
-f $DIR/AQS_overlay_2002_07.ncf \  
-configFile /home/training/config.txt \  
-s O3[1] \  
-s O38[2]*1000"
```

Note: Currently, the syntax for the command line script is slightly different than the syntax for the batch script. For example, the batch script method supports requesting a plot of hour 12 using the notation O3[1]:12, but the command line script option requires the variable name and time step be specified independently:

```
-s O3[1]  
-ts 12
```

18.2 Example Command Line Script for Windows Users

Edit the run.bat script in the VERDI_1.4 directory by right clicking on the file and selecting edit.

Figure 18-1. Location of run.bat script in Windows

The current run.bat in notepad contains a “%1” at the end that allows it to accept input following the run.bat script using the Windows run command. Unfortunately, this command does not accept directory names that have a space them, such as the “Program Files”. If you would like to enter the script command line options after run.bat, please move the data directory to C:\VERDI\data or some other similar location.

Enter the following in the Run command: cmd

When a command line window opens do the following:

```
cd C:\Program Files\VERDI_1.4\
```


```
run.bat "-f C:\\VERDI\\data\\CCTM46_P16.baseO2a.36k.O3MAX -s O3[1] -gtype tile"
```

The other option is to place the script commands within the run.bat itself. Remove the “%1” statement at the end of the run.bat that is provided in the distribution, and add the script options that you would like to use. The following run.bat contains script options that will read in the file C:\Program Files\VERDI_1.4\data\CCTM46_P16.baseO2a.36k.O3MAX, select O3[1] as the formula, and create a fast tile plot. The changes that you need to make to the run.bat are highlighted in red.

```
cd .\plugins\bootstrap
SET JAVA=..\jre1.6.0\bin\java
%JAVA% -Xmx512M -classpath ".\bootstrap.jar;.\lib\saf.core.runtime.jar;.\lib\commons-
logging.jar;.\lib\jpf-boot.jar;.\lib\jpf.jar;.\lib\log4j-1.2.13.jar" saf.core.runtime.Boot -f
C:\Program Files\VERDI_1.4\data\CCTM46_P16.baseO2a.36k.O3MAX -s O3[1] -gtype fasttile
```

Run the run.bat script by clicking on Start, then selecting Run, then either using Browse to find the run.bat or typing it in (Figure 18-2).

Figure 18-2. Submit run.bat script from Run command



Script commands that can be used for command line scripting (listed in alphabetical order) are described below. Adding support for these script commands in the Script Editor is planned for a future VERDI release.

[-alias <aliasname=definition>] defines an alias. You can define an alias by creating a definition using variable names and derived variables that are calculated using the mathematical operators described in Section 15: Mathematical Functions. The alias definition does not include the dataset name. The alias is treated like any other formula once the alias definition and the dataset to which it should be applied are specified. If you need to redefine an alias definition, you must first use the **-unalias** command. The alias definitions are saved to a verdi.alias file in your home directory. VERDI uses this type of optional file in your home directory to maintain a snapshot of the current aliases being used. The following warning will be reported if an alias is defined more than once: “WARNING: Alias <aliasname> already defined, new definition ignored.” You are also responsible for not making circular references. Use the **-printAlias** command to view what aliases are already defined.

[-animatedGIF<filename>] creates an animated GIF by doing an X Window Dump (XWD) of each of the time steps in the tile plot, then converting them to GIF images. If there are many time steps in the dataset, there will be a slight delay before you are again given control of the GUI.

[-avi<filename>] saves an animated plot of each of the time steps in the tile plot to the AVI video format.

- [-closeWindow <windowid>]** closes the window with the specified window ID.
- [-configFile <configFileName>]** specifies a configuration file for VERDI to use for configuring subsequent tile plots.
- [-copyright]** prints out copyright information for VERDI.
- [-drawDomainTicks ON|OFF]** turns the domain axis ticks on and off.
- [-drawGridLines ON|OFF]** turns the plot grid lines on and off.
- [-drawLegendTicks ON|OFF]** turns the ticks in the legend on and off.
- [-drawRangeTicks ON|OFF]** turns the range axis ticks on and off.
- [-f [[host:]<filename>]** tells VERDI to load in this dataset and make it the currently selected dataset. All datasets will stay in memory.
- [-fulldomain]** sets the VERDI domain matching the currently selected dataset to be completely selected. The currently selected dataset is usually the most recently added dataset.
- [-g <tile|fasttile|line|bar|contour>]** instructs VERDI to create a plot using the specified type and the currently selected formula's data.
- [-gtype <tile|fasttile|line|bar|contour>]** instructs VERDI to create a plot using the specified type and the currently selected formula's data (note: tile and fasttile will both generate a fasttile plot starting with VERDI version 1.4).
- [-help|fullhelp|usage]** display the information on all the command line arguments available. Each of these three versions performs the identical function.
- [-legendBins "<bin0,bin1,...,bin_n>"]** causes VERDI to use the specified numbers as breaks between colors on subsequent plots. The value of this argument is a comma-separated list of numbers. For example, **-legendBins "1,10,100,1000"** will cause plots to be created with three colors that correspond to values of 1-10, 10-100, and 100-1000. To go back to the default method for determining breaks between bins, enter **-legendBins DEFAULT**.
- [-level <level>]** sets the level range of all formulas to the single level specified.
- [-levelRange <levelMax> <levelMin>]** sets the level range of all formulas to the range specified.
- [-openProject <VERDIProjectName>]** opens a previously save VERDI project.
- [-mapName <pathname>/<mapFileName>]** causes VERDI to use the supplied *map name* instead of the default map for tile plots.
- [-printAlias]** prints existing alias definitions.
- [-project "<VERDIProjectName>"]** save dataset lists and associated formulas as a "project" for later re-use.

- [-quicktime (NEW)]** creates a Quicktime movie of the currently selected plot.
- [-quit|exit]** ends the VERDI session.
- [-raiseWindow <windowid>]** raises the window with the specified plot ID (i.e., brings it to the front).
- [-s "<formula>"]** loads the specified formula into VERDI's memory, and makes it the currently selected formula.
- [-save2ascii "<filename>"]** export data to a tab-delimited data file suitable for reading into a spreadsheet application such as Excel.
- [-saveImage "<image type>" <file name>]** saves the most recently created plot. This command works for all plot types. Supported formats include PNG, BMP, TIF, and JPG.
- [-scatter "<formula1>" "<formula2>"]** creates a scatter plot using the two formulas specified. Note that the formulas for the two components should already have been loaded into VERDI, and they are case sensitive.
- [-showWindow <windowId> <timestep>]** sets the time step of the window with the specified window ID to the specified time step. The time step must be within the allowable range for the dataset.
- [-subDomain <xmin> <ymin> <xmax> <ymax>]** sets the VERDI domain matching the currently selected dataset to the bounding box specified by its arguments. The currently selected dataset is the most recently added dataset. It is often handy to type **-subdomain** commands into VERDI's standard input if you are trying to select a very precise subdomain (such as that needed for a vertical cross-section plot).
- [-subTitle1 "<sub title 1 string>"]** allow you to control a plot's subtitles if desired. Subsequent plots will use the default subtitles, unless these arguments are used again.
- [-subTitle2"<sub title 2 string>"]** allow you to control a plot's subtitles if desired. Subsequent plots will use the default subtitles, unless these arguments are used again.
- [-subTitleFont <fontSize>]** allow you to control the font size of the subtitle of a plot.
- [-system "<system command>"]** sends the specified command to the operating system's command line.
- [-tfinal <final time step>]** sets the last time step for each formula's time-step range to the specified step number, where the first step number is denoted by 0.
- [-tinit <initial time step>]** sets the first time step for each formula's time-step range to the specified step number, where the first step number is denoted by 0.
- [-titleFont <fontSize>]** allows you to control the font size of the title of a plot.
- [-titleString "<title string>"]** sets the title for the next plot made to the specified title. Subsequent plots will use the default VERDI title, unless this argument is used again.

[-ts <time step>] sets the selected time step for each formula in VERDI's memory to the specified step number, where the first step number is denoted by 0. This will remain the selected time step until you change it. It affects only tile plots and vertical cross-section plots.

[-unalias <aliasname>] is used to undefine an alias.

[-unitString "<unit string>"] can be used to override the default unit label used for plots. The default value comes from the dataset(s) themselves.

[-vector "<U>" "<V>"] creates a vector plot with U as the left-to-right vector component and V as the down-to-up vector component. There are no background colors used for this type of plot. Note that the formulas for the two components should already have been loaded into VERDI, and they are case sensitive.

[-vectorTile "<formula>" "<U>" "<V>"] creates a vector plot with the result of "formula" as the background tiles, U as the left-to-right vector component, and V as the down-to-up vector component. Note that the formulas for the three components should already have been loaded into VERDI, and they are case sensitive.

[-version] prints out information about the VERDI version being used on the standard output stream.

[-verticalCrossPlot X|Y <row/column> (NEW)] creates a vertical cross-section plot. You indicate whether this will be an x or y cross-section plot and what row or column to use as the base.

[-windowid] prints the window ID of the currently selected plot.

19 Areal Interpolation Calculations

Before calculating the average value for a polygon segment, the area for each polygon is calculated using the projection of the grid system loaded. The system then calculates the area of overlay between each grid cell and the polygon segment.

The total contribution of a value (concentration, deposition, rainfall, etc.) from each cell for a given polygon segment is calculated using the following equation:

$$TV_i = \sum (O_{rci} * V_{rc}) \quad \text{where}$$

O_{rci} = Area of overlay of cell at row r and column c with segment i,

V_{rc} = value of cell at row r and column c, and

r and c iterate across the rows and columns of the grid.

The Average Value is calculated by dividing the total value by the area of the polygon segment:

$$\text{Average}V_i = TV_i / A_i \quad \text{where}$$

A_i = Area of the polygon segment i

20 Licenses for JAVA Libraries used by VERDI

VERDI has been developed using a number of open source Java libraries. Table 21-1 contains a list of the jar files or Java libraries that are used by VERDI, a link to where each library may be acquired, a link to the location where the license is referenced by the documentation for each library, as well as a link to each license. The distribution for VERDI contains a sub-directory called licenses. This directory contains a copy of the licenses for the open source Java libraries used by VERDI.

Table 20-1. JAVA Libraries used by VERDI

List of Java Libraries	Where to acquire software	Reference to Software License for Software	Link to license or the specific license number
JTS (java topology suite)	http://sourceforge.net/projects/jts-topo-suite/	http://www.vividsolutions.com/JTS/jts_frame.htm	http://www.gnu.org/copyleft/lessner.html
log4j-1.2.13.jar	http://www.unidata.ucar.edu/software/netcdf-java/		http://logging.apache.org/log4j/1.2/license.html
saf.core.runtime.jar	http://safr.sourceforge.net	http://www.eclipse.org/stp/cf/saf/SAFCORE.html	http://www.eclipse.org/legal/epl-v10.html
vecmath.jar	http://java3d.dev.java.net/	https://vecmath.dev.java.net/	http://www.gnu.org/licenses/old-licenses/gpl-2.0.html
geoapi	http://geoapi.sourceforge.net/	http://www.codeplex.com/GeoAPI/license	LGPL V2.1, Feb. 1999
Gt2	http://sourceforge.net/projects/geotools/	http://docs.codehaus.org/display/GEOTDOC/00+Source+License	http://www.gnu.org/licenses/lgpl-2.1.txt
hsqldb	http://hsqldb.org/		http://hsqldb.org/web/hsqldbLicense.html
jfreechart	http://sourceforge.net/projects/jfreechart/	http://developer.vrjuggler.org/browser/trunk/juggler/external/jfreechart/LICENSE.txt?rev=15441	LGPL V2.1, Feb. 1999
jscience	http://jscience.org/	http://swik.net/Jean-Marie-Dautelle	http://swik.net/License:BSD/BSD+License+Text
Piccolo 1.2	http://www.cs.umd.edu/hcil/jazz/	http://www.cs.umd.edu/hcil/jazz/download/open-source.shtml	http://opensource.org/licenses/bsd-license.php
Ucar_ma2	http://www.unidata.ucar.edu/software/netcdf-java	http://www.unidata.ucar.edu/software/netcdf-java/	http://www.gnu.org/copyleft/lessner.html
Repast symphony GIS	http://repast.sourceforge.net/		http://repast.sourceforge.net/repast-license.html

Acknowledgments

Contributions to VERDI from the community are greatly appreciated.

Data Contributions

Sample CAMx Dataset

Marco Rodriguez, CIRA at Colorado State University <http://www.cira.colostate.edu/>

Sample Mercator Projection Dataset

Tanya Otte, Atmospheric Modeling and Analysis Division, <http://www.epa.gov/amad/index.html>

Data Reader Contributions

I/O Service Provider (IOSP) Interface for CAMx:

Barron Henderson, ORISE Fellow, EPA, Ph.D. student UNC Chapel Hill

Incorporating the IOSP into netCDF netcdf-java v4.1 Library:

John Carron, Unidata, <http://www.unidata.ucar.edu/software/netcdf/index.html>